

Liquidware Labs, Inc.

ProfileUnity Help Manual

Version 4.7.1

January 2011



Disclaimer:

This document is designed as a guide to assist you and contains implementation examples that should be regarded as recommendations only. This document does not constitute any legal arrangement between Liquidware Labs, Inc. and the reader, either written or implied. This document contains proprietary information that is to be used only by Liquidware Labs, Inc. customers. Any unauthorized disclosure, copying, distribution, or use of this information is prohibited without the prior written consent of Liquidware Labs, Inc. Liquidware Labs, Inc. reserves the right to make changes to this document and the examples within it at any time to improve or enhance the support to our customers.

Trademarks and Registered Trademarks:

The product names used in this document are for identification purposes only. All trademarks and registered trademarks are the property of their respective owners. The following are trademarks that may or may not be marked in this document. Adobe and Acrobat are registered trademarks of Adobe Systems Incorporated. Citrix and XenApp are registered trademarks of Citrix Systems, Inc. in the United States. Microsoft, Internet Explorer, Office, Outlook, Outlook Express, and Windows are either trademarks or registered trademarks of Microsoft Corporation in the United States, other countries, or both. Other brands or products are service marks, trademarks, or registered trademarks of their respective holders and should be treated as such.



Contents

1.0 Installation	6
1.1 Virtual Appliance	6
1.1.1 System Requirements	6
1.1.2 Running the Installer	6
1.1.3 License Configuration	8
1.2 Standalone Installer	9
1.2.1 System Requirements	9
1.2.2 Running the Installer	9
1.2.3 License Configuration	. 15
2.0 Assignment	. 16
2.1 Group Policy Startup Script	. 17
2.2 Group Policy ProfileUnity Settings	. 18
2.3 Group Policy Logoff Script	. 25
3.0 Filter Management	. 26
3.1 Filter Editor	. 27
3.1.1 Filter Rules	27
3 1 2 Machine Class	30
3 1 3 Operating System	30
3 1 4 Connection	30
3 2 Delete	31
3.3 Summary	31
4 0 Portability Management	32
4 1 Ruleset Editor	33
4 1 1 Registry Rules	33
4 1 1 1 Operation	33
4.1.1.2 Scone	34
4.1.1.2 Goope	34
4.1.2 Filesystem Rules	34
4.1.2.1 Nosystem ration	34
4 1 2 2 Folder	34
4.1.2.2.7 older	35
1 2 Delete	35
A 3 Summary	35
5.0 Configuration Management	36
5.1 Configuration Editor	37
5.1.1 Configuration Module Editor	38
5.1.1.1 Configuration Element Order	38
5.1.2 Concents	40
5.1.2.1 Multiple Configuration Support	40
5.1.2.1 Multiple Comiguration Support	40
5 1 2 3 Security	40
5 1 2 4 Macros	40
5.1.3 Configuration Modules	44
5.1.3.1 Global Settings	45
5.1.3.2 Portability Settings	47
5.1.3.3 User Defined Aliases	49
5 1 3 4 User Defined Scripts	51
5.1.3.5 Application Launcher	52
5 1 3 6 Drive Manning	54
5.1.3.7 Environment Vars	56
5 1 3 8 Folder Redirection	57
	51



5.1.3.9 INI Files	. 59
5.1.3.10 Internet Explorer	. 61
5.1.3.11 Internet Proxy	. 63
5.1.3.12 Inventory	. 65
5.1.3.13 MAPI Profiles	. 67
5.1.3.14 Message Boxes	. 70
5.1.3.15 Microsoft Shared Fax	. 72
5.1.3.16 Office File Locations	. 74
5.1.3.17 Office Options	. 76
5.1.3.18 Outlook	. 78
5.1.3.19 Outlook Express	. 81
5.1.3.20 Path	. 86
5.1.3.21 Printers	. 87
5.1.3.22 RDP Client	. 89
5.1.3.23 Registry	. 94
5.1.3.24 Shortcuts	. 96
5.1.3.25 ThinApp	. 99
5.1.3.26 Time Sync	101
5.1.3.27 Windows Options	102
5.2 Delete	104
5.3 Summary	104
5.4 Download	104
6.0 Preferences	105
6.1 Backup	105
6.2 Restore	106
6.3 LDAP Auth	107
6.4 Inventory	109
7.0 Inventory	110
7.1 System	110
7.1.1 Delete	110
7.1.2 Details	110
7.2 ThinApp	110
7.2.1 Delete	110
7.2.2 Details	110
8.0 User Management	111
8.1 User Editor	112
8.2 Delete	113
8.3 Reset Password	113
9.0 Support / Contact Information	114
10.0 Acknowledgements	115
Appendix A - Custom Functions	116
Appendix B - Alternative Client Install Path	118
Appendix C - KiXtart: Do You Care?	119



Please report any problems with this document to <u>errata@profileunity.com</u>. Your feedback is important and we sincerely appreciate your help.



1.0 Installation

ProfileUnity is available as part of the Liquidware Labs virtual appliance and as a standalone installer. If you are using the virtual appliance please refer to section 1.1. If you are using the standalone installer please refer to section 1.2.

1.1 Virtual Appliance

If you have not loaded the virtual appliance yet, please refer to the Liquidware Labs Getting Started guide for further guidance. The Liquidware Labs virtual appliance must be installed prior to proceeding.

1.1.1 System Requirements

The ProfileUnity Client is dependent on a Microsoft domain infrastructure. The ProfileUnity Client supports machines running Windows 2000, Windows XP, Windows 2003 (R1 and R2), Windows Vista, Windows 2008 (R1 and R2), Windows 7, Terminal Server, and Citrix XenApp Server. Both 32 bit and 64 bit versions where applicable are supported. Both physical and virtual instances are also supported. Machines running the ProfileUnity Client must be members of the domain.

1.1.2 Running the Installer

The ProfileUnity Client Installer requires write permission to the netlogon share on your domain controller for proper operation. Please insure your user account has the necessary privileges prior to proceeding. To begin installation, download the ProfileUnity Client from the Administration Interface of the Liquidware Labs virtual appliance and execute it. Once execution begins, the following sequence of events will take place:





Figure 1.1.2.1: Welcome Screen

1. The Welcome Screen dialog displays as shown in Figure 1.1.2.1. Click Next to proceed.



ProfileUnity Client v4.7.1 Setup	
Choose Install Location Choose the folder in which to install ProfileUnity Client v4.7.1.	
Setup will install the ProfileUnity Client in the following folder. The ProfileUnity Client she installed to the netlogon share on your domain controller. To install in a different folder Browse and select another folder.	ould be , click
Client Destination Folder []\SERVER\NETLOGON Browse	
Nullsoft Install System v2,44	ancel

Figure 1.1.2.2: Client Destination Folder

2. You are prompted to enter the Client Destination Folder as shown in Figure 1.1.2.2. Please enter the UNC path to the netlogon share on your domain controller. Click Install after you have entered the path.

NOTE: ProfileUnity installs into a subfolder named ProfileUnity located in the netlogon share on your domain controller. The existing contents of your netlogon share remain intact and are not changed by the ProfileUnity installation process.

1.1.3 License Configuration

The ProfileUnity Client requires a valid license file to function. The following two steps are required to configure licensing for the ProfileUnity Client:

Step 1

Create an Active Directory group that contains all the valid users of ProfileUnity. Once you have setup the group in Active Directory, you will need to enter the group name in the Administration Interface of the Liquidware Labs virtual appliance.

NOTE: The ProfileUnity licensing system does not accept nested groups. ProfileUnity will only execute for users that are direct members of the specified group.

Step 2

Download your license file from the Administration Interface of the Liquidware Labs virtual appliance. Your license file should be saved to the ProfileUnity folder located in the netlogon share on your domain controller.



1.2 Standalone Installer

The ProfileUnity standalone installer will guide you through the setup of both the Management Console and the Client. Installation is straightforward and merely requires an administrator to answer a few simple prompts.

1.2.1 System Requirements

ProfileUnity Client

The ProfileUnity Client is dependent on a Microsoft domain infrastructure. The ProfileUnity Client supports machines running Windows 2000, Windows XP, Windows 2003 (R1 and R2), Windows Vista, Windows 2008 (R1 and R2), Windows 7, Terminal Server, and Citrix XenApp Server. Both 32 bit and 64 bit versions where applicable are supported. Both physical and virtual instances are also supported. Machines running the ProfileUnity Client must be members of the domain.

ProfileUnity Management Console

The ProfileUnity Management Console can be installed on a machine running Windows 2000, Windows XP, Windows 2003 (R1 and R2), Windows Vista, Windows 2008 (R1 and R2), or Windows 7. Both 32 bit and 64 bit versions where applicable are supported. Both physical and virtual instances are also supported. If necessary, the Management Console can be installed on a domain controller.

1.2.2 Running the Installer

The ProfileUnity Management Console requires your user account to have administrative privileges on the local machine for installation. Additionally, write permission to the netlogon share on your domain controller is required to install the ProfileUnity Client. Please insure your user account has the necessary privileges prior to continuing. To begin installation, execute the ProfileUnity standalone installer. The following sequence of events will take place:



🎲 ProfileUnity v4.7.1 Setup	
	Welcome to the ProfileUnity v4.7.1 Setup Wizard This wizard will guide you through the installation of ProfileUnity v4.7.1. It is recommended that you close all other applications before starting Setup. This will make it possible to update relevant system files without having to reboot your computer. Click Next to continue.
	Next > Cancel

Figure 1.2.2.1: Welcome Screen

3. The Welcome Screen dialog displays as shown in Figure 1.2.2.1. Click Next to proceed.



ProfileUnity v4.7.1 Setup	_ 🗆 X
License Agreement Please review the license terms before installing ProfileUnity v4.7.1.	
Press Page Down to see the rest of the agreement.	
If your use of this software is pursuant to a no-charge evaluation of ProfileUnity ^{IM} , the the "Evaluation License" below applies to such use. If your use of this software pursuant to an order for a paid version of ProfileUnity ^{IM} , then the "Software Licen Agreement" below applies to such use.	en 🔺 is se
LIQUIDWARE LABS, INC. EVALUATION LICENSE	
1. SCOPE OF RIGHTS.	-
If you accept the terms of the agreement, click I Agree to continue. You must accept th agreement to install ProfileUnity v4.7.1.	e
Nullsoft Install System v2,44	
< <u>B</u> ack I <u>A</u> gree Ca	ncel

Figure 1.2.2.2: License Agreement

4. The EULA displays as shown in Figure 1.2.2.2. Please read the agreement and click I Agree if you accept the terms of the agreement.



🎲 ProfileUnity v4.7.1 Setup		
Choose Components Choose which features of Profi	leUnity v4.7.1 you want to install.	
Check the components you war install. Click Next to continue.	nt to install and uncheck the comp	onents you don't want to
Select components to install:	 ✓ Management Console ✓ Client 	Description Position your mouse over a component to see its description,
Space required: 170.9MB		
Nullsoft Install System v2,44	< <u>B</u> ack	Next > Cancel

Figure 1.2.2.3: Component Selection

5. The Component Selection dialog displays as shown in Figure 1.2.2.3. Please choose the component(s) you wish to install and click Next.

NOTE: Both the Management Console and the Client need to be installed for ProfileUnity to function.



ProfileUnity v4.7.1 Setup	_ 🗆 🗙
Choose Install Location Choose the folder in which to install ProfileUnity v4.7.1.	
Setup will install the ProfileUnity Management Console in the following folder. To install different folder, click Browse and select another folder.	in a
Management Console Destination Folder	
C:\Program Files\ProfileUnity Browse	
Nullsoft Install System v2,44	ancel

Figure 1.2.2.4: Management Console Destination Folder

6. If you selected "Management Console" in the Component Selection dialog, you will be prompted to enter the Management Console Destination Folder as shown in Figure 1.2.2.4. Please enter the folder on your local machine where you would like the Management Console installed then click Next.



ProfileUnity v4.7.1 Setup	
Configure ProfileUnity Provide the details for your ProfileUnity v4.7.1 installation.	()
PostgreSQL Configuration Password: •••••• Re-enter: •••••• (Please enter the password that the 'postgres' user account will use.)	
Apache Configuration Server Port: 80 S5L Port: 443 (Please enter the ports that the bundled Apache Server will listen to.)	
Nullsoft Install System v2,44	Cancel

Figure 1.2.2.5: Configure ProfileUnity

7. If you selected "Management Console" in the Component Selection dialog, you will be prompted for the details shown in Figure 1.2.2.5. Please enter the requested information then click Next.

NOTE: The password entered is assigned to the 'postgres' account in the bundled PostgreSQL database. This password will be needed for restore operations done through the Management Console and any other tasks you wish to perform directly on the database.



ProfileUnity v4.7.1 Setup	_ 🗆 X
Choose Install Location Choose the folder in which to install ProfileUnity v4.7.1.	
Setup will install the ProfileUnity Client in the following folder. The ProfileUnity Client sho installed to the netlogon share on your domain controller. To install in a different folder, Browse and select another folder.	ould be , click
Client Destination Folder \\SERVER\NETLOGON Browse	
Nullsoft Install System v2,44	ancel

Figure 1.2.2.6: Client Destination Folder

8. If you selected "Client" in the Component Selection dialog, you will be prompted to enter the Client Destination Folder as shown in Figure 1.2.2.6. Please enter the UNC path to the netlogon share on your domain controller. Click Install after you have entered the path.

NOTE: ProfileUnity installs into a subfolder named ProfileUnity located in the netlogon share on your domain controller. The existing contents of your netlogon share remain intact and are not changed by the ProfileUnity installation process.

1.2.3 License Configuration

The ProfileUnity Client requires a valid license file to function. The following two steps are required to configure licensing for the ProfileUnity Client:

Step 1

Create an Active Directory group named ProfileUnity that contains all the valid users of ProfileUnity.

NOTE: The ProfileUnity licensing system does not accept nested groups. ProfileUnity will only execute for users that are direct members of the ProfileUnity group.

Step 2

Save your license file to the ProfileUnity folder located in the netlogon share on your domain controller. If you have not received a license file please contact the Liquidware Labs sales team.



2.0 Assignment

User accounts that should execute ProfileUnity need to have ProfileUnity assigned to them through the use of group policy. The following three steps are required to setup group policy for ProfileUnity:



2.1 Group Policy Startup Script

Assign startup.vbs as a startup script. This is a computer policy and should be applied to the OU(s) containing the computers that will execute ProfileUnity. Please see Figure 2.1.1 for further assistance.

Script Name: %systemroot%\system32\wscript.exe Script Parameters: \\entrigue.net\netlogon\ProfileUnity\startup.vbs //b



Figure 2.1.1: Group Policy Startup Script

Note: This policy should be applied to the OU(s) that contains the computers that will execute ProfileUnity. You will need to replace "entrigue.net" in the above example with the name of your domain.



2.2 Group Policy ProfileUnity Settings

Load the ProfileUnity group policy template into the group policy editor and configure the ProfileUnity settings. This is a user policy and should be applied to the OU(s) containing the user accounts that will execute ProfileUnity. Please see Figures 2.2.1 through 2.2.8 for further assistance.



Figure 2.2.1: Group Policy Add/Remove Templates



Add/Remove Templates		? >
Current Policy Templates:		
Name	Size	Modified
🖉 conf	39KB	3/25/2003 8:00
inetres	2706KB	3/8/2009 2:26 PM
system	1724KB	2/17/2007 4:04
wmplayer	66KB	3/24/2005 6:26
wuau 🗋 🗋 wuau	55KB	8/6/2009 7:19 PM
,		
Add <u>R</u> emove		Close

Figure 2.2.2: Group Policy Add/Remove Templates

Policy Template	s				? ×
Look jn:	C ProfileUnity		•	G 🔌 📂 🖽	•
My Recent Documents Desktop HYDRA	ProfileUnity.adn	n			
	File name:	\\athena\netlogon\Prof	ileLInity	-	Open
	Files of type:	Policy Templates			Cancel

Figure 2.2.3: Group Policy Add/Remove Templates

Note: The ProfileUnity group policy template is located in the folder containing the ProfileUnity agent files. By default, this is the netlogon share on your domain controller.



🚡 Group Policy Object Editor		
Eile Action <u>V</u> iew <u>H</u> elp		
← ⇒ 🔁 Add/Remove Columns		
ProfileUnity Large Icons	iquidware Labs	
E Sof List Detail Adr	n item to view its description.	Setting
En and the second seco		
Administrative Templates Administrative Templates Windows Components Administrative Templates Windows Components Administrative Templates Windows Components Start Menu and Taskba Desktop Ontrol Panel		
Shared Folders ⊕ Network ⊕ System		

Figure 2.2.4: Group Policy Filtering



Filtering		? ×
	These options allow you to filter the Administrative Templat policies.	es
Eilter by	Requirements information	
Select	the jtems to be displayed:	
🗹 A	t least Internet Explorer 5.0	_
🛛 🗹 A	t least Internet Explorer 5.0. Not supported on Windows \sim	
🛛 🛛 🗠	t least Internet Explorer 6.0 in Windows 2003 Service Pa	
🛛 🛛 🗠	t least Internet Explorer 6.0 in Windows 2003 Service Pa	
🛛 🛛 🗠	t least Internet Explorer 6.0 in Windows XP Service Pack	
- 🗹 A	t least Internet Explorer 7.0	_
	и на сили на полнити и торони и коли и ко И полнити и коли и к	
<u>S</u> ele	ect All Deselect All	
🗌 Only sh	ow <u>c</u> onfigured policy settings	
(🗖 Only sh	ow policy settings that can be fully managed)	
	OK Cancel	

Figure 2.2.5: Group Policy Filtering

Note: The ProfileUnity settings will not be visible until group policy filtering has been adjusted.



🚡 Group Policy Object Editor						
Eile Action View Help						
ProfileUnity [athena.entrigue.net]	Setting	State				
	Manager In a Dieu	Not configured				
Windows Settings Administrative Templates	Silent	Not configured				
Software Settings						
E Liquidware Labs						
ProfileUnity						
Start Menu and Taskba						
Shared Folders						
😟 💼 Network						
		-				

Figure 2.2.6: Group Policy ProfileUnity Settings



Enabled Properties	? ×
Setting Explain	
🛱 Enabled	
C Not <u>C</u> onfigured	
O <u>D</u> isabled	_
Previous Setting	
OK Cancel Apply	

Figure 2.2.7: Group Policy ProfileUnity Settings



INI File Path Properties ? 🗙
Setting Explain
斜 INI File Path
C Not <u>C</u> onfigured
© <u>D</u> isabled
UNC Path \\entrigue.net\netlogon\ProfileUnity
Previous Setting <u>N</u> ext Setting
OK Cancel Apply

Figure 2.2.8: Group Policy ProfileUnity Settings

Note: This policy should be applied to the OU(s) that contains the users that will execute ProfileUnity. You will need to replace "entrigue.net" in the above example UNC Path with the name of your domain.



2.3 Group Policy Logoff Script

Assign logoff.vbs as a logoff script. This is a user policy and should be applied to the OU(s) containing the user accounts that will execute ProfileUnity. Please see Figure 2.3.1 for further assistance.

Script Name: %systemroot%\system32\wscript.exe Script Parameters: \\entrigue.net\netlogon\ProfileUnity\logoff.vbs //b



Figure 2.3.1: Group Policy Logoff Script

Note: This policy should be applied to the OU(s) that contains the users that will execute ProfileUnity. You will need to replace "entrigue.net" in the above example with the name of your domain.



3.0 Filter Management

Filters are used to limit the scope of configuration elements. As configuration elements are processed during ProfileUnity execution, the filter assigned to each configuration element is evaluated. If the filter evaluation returns true, the configuration element is applied. If the filter evaluation returns false, the configuration element is skipped. Filters allow a single ProfileUnity configuration to be applied differently to multiple client machines and users.

For example, suppose you want to map the G:\ drive to the finance share on your file server for all employees in your accounting department. You could first create a filter that tests for membership in the accounting group. You could then assign this filter to the configuration element that maps the G:\ drive to your file server's finance share. The filter will only allow the G:\ drive to be mapped for members of the accounting group.

Creating, modifying, deleting, and summarizing filters is done through the filter management user interface, shown in figure 3.0.1.

New Filter	Name	Created	Modified
Summary Edit Delete Copy	Domain Admins	10/26/2009	10/26/2009
	Members of Group Domain Admins		
Summary Edit Delete Copy	Liquidware Labs	10/26/2009	10/26/2009
	Members of Group Liquidware Labs		
Summary Edit Delete Copy	Null Filter	10/26/2009	10/26/2009
	Filter Never Fires		
Summary Edit Delete Copy	Test Filter 1	10/19/2009	10/26/2009
	Testing		
Displaying 1-4 of 4			

Figure 3.0.1: Filter Management Interface

NOTE: Configuration elements can also be assigned the Global Settings filter. The Global Settings filter is a predefined filter that is not displayed in the filter management user interface. This filter cannot be deleted and always returns true. Any configuration element you assign the Global Settings filter to will always be applied.



3.1 Filter Editor

The filter editor, shown in figure 3.1.1, is where all filter configuration takes place. Selecting the following options in the filter management interface invokes the filter editor:

- New Filter Creates a new filter
- Edit Modifies an existing filter
- Copy Duplicates an existing filter

Create/Edit Filter					
Filter Name: Filter Comment: Rule Aggregate:	Domain Admins Members of Group Do AND (All Rules)	omain Admins			
	Filter	Rules			
Condition	Match Exactly)	¥alue	Add		
Group Membership	Is (Exactly)	Domain Adm	nins <u>Remove</u>		
Machine Class ✓ Desktop / Laptop ✓ Terminal Server ✓ Member Server ✓ Domain Controller	0per- 2000 ✓ XP ✓ 2003	ating System Vista 2008 7	Connection IAN Dial-up/VPN		
	G Indicates F	Required Field et Cancel			

Figure 3.1.1: Filter Editor Interface

Filters consist of the following elements: a filter name, filter rules, machine classes, operating system types, and connection types.

3.1.1 Filter Rules

Filter rules are comprised of a condition, match, value triplet. A filter can have multiple filter rules. The logic used to evaluate multiple filter rules is based on the Rule Aggregate option. If the Rule Aggregate option is set to AND (All Rules), all rules must evaluate true for the filter to return true. If the Rule Aggregate option is set to OR (Any Rule), the filter will return true if any rule evalutes true. The Rule Aggregate option applies to all rules in a filter. It is not possible to specify AND logic for some rules and OR logic for other rules. Table 3.1.1.1 lists the possible conditions and provides example values.



Condition	Value
Group Membership	Tests for membership in specified group.
	Example: Value: Accounting
Primary Group	Returns true for users that are members of the accounting group. Tests value against user's assigned Primary Group.
	Example:
	Match: Is (Exactly) Value: Domain Users
	Returns true for users with Domain Users assigned as the Primary Group.
User Name	Tests value against user's logon name.
	Example: Match: Is (Exactly)
	Value: GPBurdell Returns true if the user's logon name is GPBurdell.
TCP/IP Address	Tests value against the IP address assigned to the client machine. If multiple IP addresses are assigned to the client, the first four IP
	addresses are tested.
	Match: Is (Exactly)
	Returns true if the client machine has IP Address 192.168.1.1.
	Example: Match: Begins With
	Value: 10.1 Returns true if the first two octets of the client IP Address is 10.1.
Host Name	Tests value against the fully qualified TCP/IP hostname.
	Example: Match: Is (Exactly)
	Value: atl-001.xyz.com Returns true if the client machine has atl-001.xyz.com assigned as
Computer Name	the TCP/IP hostname. Tests value against the NetBIOS computer name.
	Example:
	Match: Is (Exactly) Value: ATL-001
MAC Address	Returns true if the client machine is named ATL-001. Tests value against the address of the network adapter.
	Example: Match: Is (Exactly)
	Value: 00306E053085
	00306E053085.



Domain	Example: Match: Begins With Value: 00306E Returns true if the client's network adapter has an address that begins with 00306E. Since the first six digits of a MAC address identify the vendor, this filter would return true for network adapters manufactured by Hewlett Packard. Tests value against the domain the client machine is a member of.
Logon Domain	Example: Match: Is (Exactly) Value: XYZ Returns true if the client machine is a member of the domain or workgroup XYZ. Tests value against the domain the user is logged on to.
Logon Server	Example: Match: Is (Exactly) Value: ABC Returns true if the user is logged on to domain ABC. Tests value against the name of the logon server.
Site	Example: Match: Is (Exactly) Value: ADC01 Returns true if the server named ADC01 processed the user's logon. Tests value against the name of the Active Directory site the client machine resides in.
TS Client Name	Example: Match: Is (Exactly) Value: Default-First-Site-Name Returns true if the client machine resides in site Default-First-Site- Name. Tests value against the NetBIOS name of the client machine connecting to the terminal server.
TS Session Name	Example: Match: Is (Exactly) Value: ATL-001 Returns true if the client machine connecting to the terminal server is named ATL-001. Tests value against the session name assigned to the client machine connecting to the terminal server.
	Example: Match: Is (Exactly) Value: RDP-Tcp#48 Returns true if the client machine connecting to the terminal server is assigned session name RDP-Tcp#48.
	Example: Match: Begins With Value: RDP



	Returns true for all client machines connecting to the terminal server via the RDP protocol.
Custom Function OU (User)	Example: Match: Begins With Value: ICA Returns true for all client machines connecting to the terminal server via the ICA protocol. Allows filter logic to be extended through the use of a custom written function. Please see Appendix A for further assistance. Tests value against the name of the Active Directory OU the user's account resides in.
OU (Computer)	Example: Match: Is (Exactly) Value: OU=Test,DC=xyz,DC=com Returns true if the user's account resides in OU=Test,DC=xyz,DC=com. Tests value against the name of the Active Directory OU the client machine resides in.
View Client Name	Example: Match: Contains Value: OU=Atlanta Returns true if the OU the client machine resides in contains OU=Atlanta. Tests value against the name of the client machine connecting to the VMware View session.
	Example: Match: Is (Exactly) Value: ATL-001 Returns true if the client machine connecting to the VMware View session is named ATL-001. Table 3.1.1.1: Filter Rules

3.1.2 Machine Class

Allows filters to include or exclude different machine classes. Available choices are Desktop/Laptop, Terminal Server, Member Server, and Domain Controller. The Desktop/Laptop machine class will return true for all client machines that are not Terminal Servers, Member Servers, or Domain Controllers.

3.1.3 Operating System

Allows filters to include or exclude different operating systems.

3.1.4 Connection

Allows filters to include or exclude different network connection types. Available choices are LAN and Dial-up. The logic used to determine the connection type is based on active Remote Access Service (RAS) connections. If the client machine has one or more active RAS connections, it is assumed the user is on a Dial-up connection.



NOTE: Please remember to save your filter when you have finished defining its configuration. If you leave the filter editor without saving, all changes will be discarded. If you attempt to leave the filter editor and you have unsaved changes, the warning shown in figure 3.1.2 will be displayed.

Microsoft	: Internet Explorer				
2	Navigating away from this page will discard all unsaved changes.				
~	Would you like to save your changes before leaving?				
	Press OK to save, Cancel to discard.				
	OK Cancel				

Figure 3.1.2: Save Warning

3.2 Delete

Selecting delete will permanently delete the filter. Filters can only be deleted if they are not used by any of your configurations. If you attempt to delete a filter still in use by one or more of your configurations, you will receive the warning shown in figure 3.2.1.

Filter In	Use A filter cannot be deleted while it is in use. This filter is currently in use by the following 1 configuration(s): 1) Demo Inventory		

3.3 Summary

Summary allows you to generate either a PDF or text summary report of your filter configuration.



4.0 Portability Management

ProfileUnity solves the difficulties in making personal user profile data available across multiple Windows sessions. When a user logs on to a Windows session, his/her personal user profile settings are instantly pulled across the network in seconds. Customized settings such as application level customization, user created spellchecker data, Outlook signatures, desktop wallpaper, and much more are instantly made available for the user regardless if the machine is a VMware VM, XenDesktop, thin, or traditional Windows desktop.

By default, a large amount of data is stored in a user's profile. However, not all of this data is necessary for a robust and complete user experience. ProfileUnity is granular by design, allowing you to set rules and choose what profile data is to be made portable. This makes for speedy logon times, reduces profile corruption instances, and eliminates the needless transfer of large amounts of data over the network.

With ProfileUnity, making user profile data portable is a two step process. First, you define rulesets through the Portability Management interface. Rulesets control the portions of the user profile that will follow the user around the network. Second, once your rulesets are defined, the Portability Settings configuration module is used to control how user profile data is stored and retrieved from the network. Please see section 5.1.3.2 for assistance with the Portability Settings configuration module.

ProfileUnity includes predefined rulesets designed to manage popular settings. These predefined rulesets can be used to quickly setup portability with minimal configuration. You can modify these predefined rulesets as well as create your own rulesets.

Creating, modifying, deleting, and summarizing rulesets is done through the portability management user interface, shown in figure 4.0.1.

New Ruleset	Name	<u>Created</u>	Modified
Summary Edit Delete Copy	3rd Party Applications	07/23/2008	07/23/2008
Summary Edit Delete Copy	Application Data	09/05/2008	09/05/2008
Summary Edit Delete Copy	Certificates	07/29/2008	07/29/2008
Summary Edit Delete Copy	Front Page	06/30/2008	06/30/2008
Summary Edit Delete Copy	FS Cleanup Test	10/19/2009	10/19/2009
Summary Edit Delete Copy	Internet Explorer	06/30/2008	07/29/2008
Summary Edit Delete Copy	MAPI Profiles	06/30/2008	07/23/2008
Summary Edit Delete Copy	Office	06/30/2008	06/30/2008
Summary Edit Delete Copy	Passwords	06/30/2008	06/30/2008
Summary Edit Delete Copy	Printers	06/30/2008	07/23/2008
Displaying 1-10 of 14			1 <u>2</u> <u>Next</u>

Figure 4.0.1: Portability Management Interface



4.1 Ruleset Editor

The ruleset editor, shown in figure 4.1.1, is where all ruleset configuration takes place. Selecting the following options in the portability management interface invokes the ruleset editor:

- New Ruleset Creates a new ruleset
- Edit Modifies an existing ruleset
- Copy Duplicates an existing ruleset

reate/Edit Ruleset						
	Ruleset Name:]🖸			
Rule	Ruleset Comment:					
			-			
		Registry Rules				
Operation	Scope	Path				
Merge 💌	Tree 💌		Add			
		Filesystem Rules				
Operation	Folder	Filesystem Rules Path				
Operation Merge	Folder Application Data	Filesystem Rules Path	Add			
Operation Merge	Folder Application Data	Filesystem Rules Path	Add			
Operation Merge	Folder Application Data	Filesystem Rules Path	Add			
Operation Merge	Folder Application Data	Filesystem Rules Path Table Filesystem Rules Path Table Path Table Path Table Path Path Path Path Path Path Path Path	Add			
Operation Merge	Folder Application Data	Filesystem Rules Path IIIIIIIIIIIIIIIIIIIIIIIIIIIIIIIIIIII	Add			
Operation Merge	Folder Application Data	Filesystem Rules Path Filesystem Rules Path Reset Cancel	Add			

Figure 4.1.1: Ruleset Editor Interface

User profiles are comprised of two types of data: registry settings and files/folders. Rulesets handle these data types with registry and filesystem rules respectively. Rulesets consist of the following elements: a ruleset name, registry rules, and filesystem rules.

4.1.1 Registry Rules

Registry rules are comprised of an operation, scope, path triplet. A ruleset can have multiple registry rules. Registry rules allow granular storage and retrieval of values located under the HKEY_CURRENT_USER registry key.

4.1.1.1 Operation

- Merge Saved data is merged with existing data during restore.
- Replace Existing data is replaced with saved data during restore.
- Exclude Data is excluded from save and restore.



4.1.1.2 Scope

- Tree Path specifies a key. Specified key and values, subkeys, and subkey values.
- Key Path specifies a key. Specified key and values only, no subkeys or subkey values.
- Value Path specifies a value. Specified value only.

4.1.1.3 Path

The Path specifies the key or value located under the HKEY_CURRENT_USER registry key containing the user profile data that should be saved and restored.

NOTE: The Path is relative to HKEY_CURRENT_USER. Your entries should not begin with HKEY_CURRENT_USER since ProfileUnity adds this portion of the path by design.

Example: Operation: Merge Scope: Tree Path: Software\Microsoft\Office

The above example will save and restore the registry values contained in the HKEY_CURRENT_USER\software\Microsoft\Office key and all subkeys. During restore, existing data will be overwritten with the saved values.

4.1.2 Filesystem Rules

Filesystem rules are comprised of an operation, folder, path triplet. A ruleset can have multiple filesystem rules. Filesystem rules allow granular storage and retrieval of files/folders located in the user profile.

4.1.2.1 Operation

- Merge Saved data is merged with existing data during restore.
- Replace Existing data is replaced with saved data during restore.
- Exclude Data is excluded from save and restore.

4.1.2.2 Folder

- Application Data Specified path is relative to the Application Data shell folder.
- Cookies Specified path is relative to the Cookies shell folder.
- Desktop Specified path is relative to the Desktop shell folder.
- Favorites Specified path is relative to the Favorites shell folder.
- History Specified path is relative to the History shell folder.
- Personal (My Documents) Specified path is relative to the Personal shell folder.
- Program Group Specified path is relative to the Programs shell folder.
- Recent Specified path is relative to the Recent shell folder.
- Send To Specified path is relative to the SendTo shell folder.
- Start Menu Specified path is relative to the Start Menu shell folder.
- Startup Group Specified path is relative to the Startup shell folder.
- User Profile Specified path is relative to the user profile root folder.
- Local AppData Specified path is relative to the Local AppData shell folder.
- Program Files Specified path is relative to the %programfiles% environment variable.
- System Drive Specified path is relative to the %systemdrive% environment variable.
- System Root Specified path is relative to the %systemroot% environment variable.



4.1.2.3 Path

The Path specifies the file/folder containing the user profile data that should be saved and restored. The Path is relative to the entry specified in Folder.

NOTE: Filesystem rules with an empty Path component include all files/folders under the entry specified in Folder.

Example:

Operation: Merge Folder: Application Data Path: Microsoft

The above example will save and restore the files/folders contained in the **Microsoft** folder located in the **Application Data** shell folder. During restore, existing data will be overwritten with the saved data.

NOTE: Please remember to save your ruleset when you have finished defining its configuration. If you leave the ruleset editor without saving, all changes will be discarded. If you attempt to leave the ruleset editor and you have unsaved changes, the warning shown in figure 4.1.2 will be displayed.

Microsoft Internet Explorer						
2	Navigating away from this page will discard all unsaved changes.					
	Would you like to save your changes before leaving?					
	Press OK to save, Cancel to discard.					
	OK Cancel					

Figure 4.1.2: Save Warning

4.2 Delete

Selecting delete will permanently delete the ruleset. Rulesets can only be deleted if they are not used by any of your configurations. If you attempt to delete a ruleset still in use by one or more of your configurations, you will receive the warning shown in figure 4.2.1.



4.3 Summary

Summary allows you to generate either a PDF or text summary report of your ruleset configuration.



5.0 Configuration Management

Configurations are used to control ProfileUnity execution. During user logon, the ProfileUnity client reads your configuration files and applies the settings to your client machines. Creating, modifying, deleting, summarizing, and downloading configurations is done through the configuration management user interface, shown in figure 5.0.1.

New Configuration	Name	<u>Created</u>	Modified
Summary Edit Delete Copy	Default	10/08/2009	10/21/2009
<u>Download</u>	Configuration Created 10/08/2009 04:18 AM		
Summary Edit Delete Copy	Demo Inventory	10/22/2009	10/26/2009
<u>Download</u>	Configuration Created 10/22/2009 08:44 PM		
Summary Edit Delete Copy	Folder Redirection Sync Test	10/21/2009	10/23/2009
<u>Download</u>	Configuration Created 10/21/2009 10:31 PM		
Summary Edit Delete Copy	FS Cleanup Test	10/19/2009	10/19/2009
<u>Download</u>	Configuration Created 10/19/2009 02:31 PM		
Summary Edit Delete Copy	Inventory	10/20/2009	10/20/2009
Download	Configuration Created 10/20/2009 02:35 PM		
Displaying 1-5 of 5			

Figure 5.0.1: Configuration Management Interface


5.1 Configuration Editor

The configuration editor, shown in figure 5.1.1, is where all configuration settings are entered. Selecting the following options in the configuration management interface invokes the configuration editor:

- New Configuration Creates a new configuration
- Edit Modifies an existing configuration
- Copy Duplicates an existing configuration

Configuration Module	_	
🔮 Global Settings	Configuration	Management
🥺 Portability Settings	Peturo to Coofiguration	Management Home
😫 User Defined Aliases	Recarried Coningaration	I Management nome
👲 User Defined Scripts	Default	
🛗 Application Launcher		
😥 Drive Mapping		
💽 Environment Vars	Configurat	ion Name: Default
🗟 Folder Redirection	Configuration	Comment: Configuration Created 10/08/2009 04:18 AM
🗐 INI Files		
🥌 Internet Explorer		
Internet Proxy		
🛃 Inventory		
😂 MAPI Profiles	Configurati	ion Notes:
i Message Boxes		
Microsoft Shared Fax		
🔯 Office File Locations		
Office Options		
Outlook		Require Group Membership for Execution
🇐 Outlook Express		Group: N/A
🛅 Path		aroapi pini
🍓 Printers		La La confét Uson (é Duraciona Acusachus)
🝓 RDP Client		Cogori User in Running Asynchron
🔊 Registry		J♥ Disable Group Token-Cache
🐬 Shortcuts		
🔗 Time Sync		记 Indicates Required Field
😼 Windows Options		
		Save Reset

Figure 5.1.1: Configuration Editor Interface

A configuration is comprised of configuration modules. When the editor is invoked, the available configuration modules are listed in the menu located on the left hand side.



5.1.1 Configuration Module Editor

All configuration modules other than the Global Settings module permit you to make multiple entries. Each entry is referred to as a configuration element. Selecting any configuration module that permits multiple entries invokes the configuration module editor. When no configuration elements are defined for a configuration module, the configuration module editor will display as shown in figure 5.1.1.1.

Default		Drive Mapping
There are currently no settings defined. Select "Add" to create a new entry.		
	Add Save Reset	



Selecting Add will create a new configuration element. Each configuration element you create is displayed in the configuration module editor. Figure 5.1.1.2 shows the **Drive Mapping** configuration module with multiple configuration elements defined.

Default	Drive Mapping
Highest Priority Fi	ilter: Global Settings
🛉 🕈 Insert Edit Delete Copy 🗛	Action: Disconnect All
Fi	ilter: Liquidware Labs
A	Action: Map G: (Not Persistent, Not Hidden)
U	INC Path: \\ATLF502\Shared\$
+ Insert Edit Delete Copy E	xplorer Label: Shared Drive
Fi	ilter: Global Settings
A	Action: Map H: (Not Persistent, Not Hidden)
Lowest Priority U	INC Path: \\ATLF501\@userid\$
🛉 🕈 Insert Edit Delete Copy 🖪	xplorer Label: Home Drive
Displaying 1-3 of 3	
	Add Save Reset

Figure 5.1.1.2: Populated Configuration Module Editor

5.1.1.1 Configuration Element Order

Configuration elements are processed in linear order starting with the first configuration element and ending with the last configuration element. The configuration module editor indicates the processing order with the labels "Highest Priority" and "Lowest Priority". The first configuration element is labeled "Highest Priority" while the last configuration element is labeled "Lowest Priority". The "Highest Priority" and "Lowest Priority" labels are used to indicate processing order only and do not indicate which configuration element takes precedence. Configuration element order can best be explained with the following two examples.



Drive Mapping Order Example:

New Configuration		Drive Mapping
	Filter: Global Settings	
	Action: Map H: (Not Persistent)	
Highest Priority	UNC Path: \\SVR-A\share	
🛉 🕴 Insert Edit Delete Copy	Explorer Label: N/A	
	Filter: Global Settings	
	Action: Map H: (Not Persistent)	
Lowest Priority	UNC Path: \\SVR-B\share	
🛉 🕴 Insert Edit Delete Copy	Explorer Label: N/A	
Displaying 1-2 of 2		

Figure 5.1.1.3: Drive Mapping Order

Figure 5.1.1.3 displays the Drive Mapping configuration module with two configuration elements defined. The first configuration element maps the H: drive to a share located on SRV-A. The second configuration element maps the H: drive to a share located on SRV-B. When the first configuration element is processed, the H: drive is mapped to SRV-A. The second configuration element will be unable to map the H: drive to SRV-B since the H: drive is already mapped to SRV-A. In this example, the first configuration element processed wins.

Environment Vars Order Example:

New Configuration		Environment Vars
	Filter: Global Settings	
	Action: Set Variable	
Highest Priority	Variable: TEST	
🛉 🕈 Insert Edit Delete Copy	Value: FIRST	
	Filter: Global Settings	
	Action: Set Variable	
Lowest Priority	Variable: TEST	
🛉 🕴 Insert Edit Delete Copy	Value: SECOND	
Displaying 1-2 of 2		

Figure 5.1.1.4: Environment Vars Order

Figure 5.1.1.4 displays the Environment Vars configuration module with two configuration elements defined. Both elements modify the environment variable TEST. When the first configuration element is processed, the TEST environment variable is set to the value FIRST. When the second configuration element is processed, the TEST environment variable is set to the value SECOND. In this example, the last configuration element processed wins.

The order of configuration elements is important and can greatly impact expected results. You can change the processing order of a configuration element by selecting the $\frac{1}{2}$ (Move Up) and $\frac{1}{2}$ (Move Down) icons next to the entry. Additionally, a new configuration element can be inserted above a current entry by selecting the <u>Insert</u> link next to the entry.



NOTE: Please remember to save your configuration module settings when you have finished defining them. If you leave the configuration module editor without saving, all changes will be discarded. If you attempt to leave the configuration module editor and you have unsaved changes, the warning shown in figure 5.1.1.5 will be displayed.

Microsof	t Internet Explorer
2	Navigating away from this page will discard all unsaved changes.
~	Would you like to save your changes before leaving?
	Press OK to save, Cancel to discard.
	Cancel

Figure 5.1.1.5: Save Warning

5.1.2 Concepts

Prior to creating a configuration, you should familiarize yourself with the concepts presented in sections 5.1.2.1 through 5.1.2.4.

5.1.2.1 Multiple Configuration Support

ProfileUnity optionally supports multiple configurations. Multiple configurations allow your settings to be grouped into logical boundaries. For example, in a large organization with multiple IT departments, each department can have its own configuration. Members of one department can modify their settings without disturbing the settings of any other department.

When ProfileUnity executes, it obtains the list of available configurations from the authenticating domain controller. If the configuration **Default** is present, it is always processed first. The remaining configurations are then processed in alphabetical order.

5.1.2.2 Escaping Reserved Characters

The characters @, %, and \$ are reserved characters. If you want to use these characters in your configuration, you will need to use @@, %%, or \$\$ instead. For example, if you want to use the email address user@domain.com, you will need to use user@@domain.com instead.

5.1.2.3 Security

ProfileUnity executes in the security context of the user logging on to the network. Privileges are never elevated during execution, insuring your security policies are preserved. Maintaining security is not without cost. ProfileUnity is only able to modify settings the user can modify. You will need to consider the impact security will have on your configuration. For example, attempting to modify a registry value that the user does not have permission to will fail.

5.1.2.4 Macros

Macros can be used in your configuration anywhere an expression is expected. During logon, these macros expand into values based on their definition. For example, when a user named GPBurdell logs on to a client machine, the @userid macro expands into GPBurdell. Macros have many practical uses. The UNC path, \\your-server\@userid, can be used to map a drive to a per-user share. The @lserver macro can be used to set the system time on legacy clients from the authenticating domain controller. Table 5.1.2.4 lists the supported macros and their definitions. For your convenience, the online help system also lists this table.



Macro	Definition
@ADDRESS	Address of the network adapter
@BUILD	Build number of the operating system
@COLOR	Current console color setting
@COMMENT	User comment
@CPU	Name of the CPU (e.g.: "Intel Pentium III")
@CRLF	Carriage-return + Line-feed
@CSD	CSD information (e.g.: "Service Pack 1")
@CURDIR	Current directory
@DATE	Date (in the format YYYY/MM/DD)
@DAY	Day of the week (Monday, Tuesday, and so on)
@DOMAIN	Domain or workgroup the computer belongs to
@DOS	Version of Windows NT
@ERROR	Return code of the most recent command or function. A return
	code of 0 means the command or function was successful. Any
	other value indicates an error.
@FULLNAME	Full name of current user
@HOMEDIR	Short name of the directory part of home directory
@HOMEDRIVE	Drive letter of drive containing home directory
@HOMESHR	Server and share name part of home directory
@HOSTNAME	Fully qualified TCP/IP host name (including TCP/IP domain
	name)
@INWIN	Operating system: 1 = Windows NT; 2 = Windows 9x
@IPADDRESSx	TCP/IP address (possible values for x are 0 - 3)
@KIX	KiXtart product name and version
@LANROOT	Directory where network software resides (usually
	Systemroot\System32)
	Logon domain
@LDRIVE	Drive that is redirected to \\logonserver\NETLOGON
	Version of network software
@LOGONMODE	logon sequence
@LONGHOMEDIR	Long name of the directory part of home directory
@LSERVER	Logon server
@MAXPWAGE	Maximum password age
@MDAYNO	Day of the month (1-31)
@MHZ	Approximation of the CPU speed. Not available on Windows 9x.
@MONTHNO	Months since January (1-12)
@MONTH	Name of the month
@MSECS	Milliseconds part of the current time
@PID	Process ID of the KiXtart process
@PRIMARYGROUP	Current user's primary group
@PRIV	User's privilege level (GUEST, USER, ADMIN)
@PRODUCTSUITE	OS suite. Combination of any of the following values:
	1 - "Small Business"
	2 - Enterprise
	4 - DackOllice
	6 - CommunicationServer
	22 "Small Business (Bostricted)"
	61 - "EmboddodNT"
	128 - "DataCenter"
	256 - "Single user Terminal Server"
	512 - "Home Edition"



@PRODUCTTYPE

1024 - "Blade Server" 2048 - "Embedded (Restricted)" 4096 - "Security Appliance" 8192 - "Storage Server" 16384- "Compute Cluster Server" OS type. Possible values: "Windows 2000 Professional" "Windows 2000 Server" "Windows 2000 Domain Controller" "Windows XP Home Edition" "Windows XP Professional" "Windows XP Professional Tablet PC" "Windows XP Media Center Edition" "Windows XP Starter Edition" "Windows Fundamentals for Legacy PCs" "Windows Server 2003" "Windows Server 2003 Domain Controller" "Windows Server 2003 R2" "Windows Server 2003 R2 Domain Controller" "Windows Vista Starter Edition" "Windows Vista Home Basic Edition" "Windows Vista Home Basic Edition N" "Windows Vista Home Premium Edition" "Windows Vista Business Edition" "Windows Vista Business Edition N" "Windows Vista Enterprise Edition" "Windows Vista Ultimate Edition" "Windows Server 2008 (R2)" "Windows Server 2008 (R2) Core" "Windows Server 2008 (R2) Small Business Edition" "Windows Server 2008 (R2) Enterprise Edition" "Windows Server 2008 (R2) Enterprise Edition Core" "Windows Server 2008 (R2) Datacenter Edition" "Windows Server 2008 (R2) Datacenter Edition Core" "Windows Server 2008 (R2) Enterprise Edition for Itanium" "Windows Server 2008 (R2) Web Server Edition" "Windows Server 2008 (R2) Web Server Edition Core" "Windows Server 2008 (R2) Compute Cluster Edition" "Windows Server 2008 (R2) Home Edition" "Windows Storage Server 2008 (R2) Express Edition" "Windows Storage Server 2008 (R2) Standard Edition" "Windows Storage Server 2008 (R2) Enterprise Edition" "Windows Storage Server 2008 (R2) Small Business Edition" "Windows Server 2008 (R2) Essential Business Server" "Windows Server 2008 (R2) Essential Business Server Premium" "Windows Server 2008 (R2) Essential Business Server Management" "Windows Server 2008 (R2) Essential Business Messaging" "Windows Server 2008 (R2) Essential Business Security" "Windows Server 2008 (R2) Hyper-V" "Windows Server 2008 (R2) Foundation" "Windows 7 Starter Edition" "Windows 7 Starter Edition N"



	"Windows 7 Home Basic Edition"
	"Windows 7 Home Basic Edition N"
	"Windows 7 Home Premium Edition"
	"Windows 7 Home Premium Edition N"
	"Windows 7 Business Edition"
	"Windows 7 Business Edition N"
	"Windows 7 Professional Edition"
	"Windows 7 Professional Edition N"
	"Windows 7 Enterprise Edition"
	"Windows 7 Enterprise Edition N"
	"Windows 7 Ultimate Edition"
	"Windows 7 Ultimate Edition N"
@PWAGE	Password age
@RAS	Number of active Remote Access Service (RAS) connections
@RESULT	Returns command specific information (e.g.: the drive letter of an
	automatic redirection command)
@RSERVER	KXRPC server used for the current session
@SCRIPTDIR	Directory of current script
@SCRIPTEXE	Name of KiXtart executable ("KIX32.EXE", "WKIX32.EXE")
@SCRIPTNAME	Name of current script
@SERROR	Error text corresponding with @ERROR
@SID	Current user's Windows NT Security Identifier (SID)
@SITE	Name of the site in which the system resides
@STARTDIR	Directory from which KiXtart was started
@SYSLANG	Full English name of the language of the operating system
	specified in the format defined by ISO Standard 639 (example :
	"0413Dutch (Standard)")
@TICKS	Returns the number of milliseconds that have elapsed since the
	system was started
@TIME	Current time (in the format HH:MM:SS)
@USERID	Current user's Windows NT user ID
@USERLANG	Full English name of the language selected by the current user
	specified in the format defined by ISO Standard 639 (example :
	"0413Dutch (Standard)")
@WDAYNO	Days since Sunday (1 - 7)
@WKSTA	Computer name
@WUSERID	Current user's Windows user ID
@YDAYNO	Days since January 1 (1 - 365)
@YEAR	Current year
	Table 5.1.2.4: Macros



5.1.3 Configuration Modules

A configuration is comprised of configuration modules. Each configuration module is designed to accomplish a specific task. The following configuration modules are available:

- Global Settings
- Portability Settings
- User Defined Aliases
- User Defined Scripts
- Application Launcher
- Drive Mapping
- Environment Vars
- Folder Redirection
- INI Files
- Internet Explorer
- Internet Proxy
- Inventory
- MAPI Profiles
- Message Boxes
- Microsoft Shared Fax
- Office File Locations
- Office Options
- Outlook
- Outlook Express
- Path
- Printers
- RDP Client
- Registry
- Shortcuts
- Time Sync
- Windows Options

NOTE: Configuration modules are processed in the order they are listed above. This can impact the expected results. For example, since the Drive Mapping module is processed after the Application Launcher module, the Application Launcher module will not have access to drives mapped by the Drive Mapping module.



5.1.3.1 Global Settings

The Global Settings configuration module is used to define parameters for a configuration that apply to all users.

Default			Global Settings
Configuration Name:	Default	C	
Configuration Comment:	Configuration Created 10/08/2009 04:18 AM		
Configuration Notes:			
	Require Group Membership for Execution		
	Group: N/A		
	☑ Disable Group Token-Cache		
	🤤 Indicates Required Field		
	Save Reset		

Figure 5.1.3.1: Global Settings

Configuration Name:

Enter a name that helps you identify your configuration.

NOTE: When ProfileUnity executes, it obtains the list of available configurations from the authenticating domain controller. If a configuration named **Default** is present, it is always processed first. The remaining configurations are processed in alphabetical order.

Configuration Comment:

Enter a description that helps you identify your configuration.

Configuration Notes:

Enter notes that help you identify your configuration.

Require Group Membership for Execution:

Selecting this option restricts execution of this configuration to members of the global group specified in the **Group** field.



Disable Group Token-Cache:

ProfileUnity caches group membership information in the registry. Caching the group membership information reduces the amount of network traffic generated during user logon. However, if an existing group is renamed, the token-cache will not immediately update itself. If you experience problems filtering by Group Membership, selecting this option will disable the cache.



5.1.3.2 Portability Settings

The Portability Settings module is used to control the storage and retrieval of personal user preferences during logoff and logon. This module works in conjunction with the rulesets defined through the Portability Management interface. Please see section 4.0 for assistance with rulesets.

Default		Portability Settings - Edit
Filter:	Global Settings	
Action:	Save/Restore 💌	
Ruleset:	3rd Party Applications 💌	
Save Path:		
UID:	iwelenwu7vomk5e	
	OK Cancel	

Figure 5.1.3.2: Portability Settings

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Action:

Select one of the following actions:

- Save/Restore During logoff settings are saved and during logon settings are restored.
- Save During logoff settings are saved.
- Restore During logon settings are restored.

Ruleset:

Select the name of the ruleset you want assigned to this configuration element. Please see section 4.0 for assistance with rulesets. This option does not apply if you choose Restore for the action.

Save Path:

The Save Path designates the UNC name of the location ProfileUnity will use to store/retrieve the portability settings.

UID:

The UID is a unique identifier that is automatically generated by ProfileUnity. Normally, the UID does not need to be changed. The UID is used for file name generation.

NOTE: ProfileUnity will create a compressed file named "UID.7z" in the location specified by the Save Path. This file will be used by ProfileUnity to store/retrieve the portability settings.



Example: Filter: Global Settings Action: Save/Restore Ruleset: MAPI Profiles Save Path: H:_Settings UID: v84lktv1tat6lan

The above example will save the settings defined by the **MAPI Profiles** ruleset at logoff and restore them at logon. The settings will be stored and retrieved from a file named **v84lktvltat6lan.7z** located in the **H**: \ **Settings** folder.

NOTE: This example assumes the H: drive is mapped to a network share. It is also possible to use a UNC name for the Save Path.

Example:

Filter: Global Settings Action: Save/Restore Ruleset: Application Data Save Path: \\ATLFS02\@userid\Citrix_Profile UID: wjdemgosiitd1vs

The above example will save the settings defined by the Application Data ruleset at logoff and restore them at logon. The settings will be stored and retrieved from a file named wjdemgosiitdlvs.7z located in the \\ATLFS02\@userid\Citrix_Profile folder. This example leverages the macro @userid. When ProfileUnity executes, the @userid macro is expanded into the username.



5.1.3.3 User Defined Aliases

User Defined Aliases are used to retrieve information from your domain controllers about the current user's account. The values retrieved are available for use throughout your ProfileUnity configuration.

Default		User Defined Aliases - Edit
Filter:	Global Settings	
Alias Type:	Simple Alias	
Alias Name:		
Full Name Format:	First Last	
Simple Alias Field:	First Name	
Advanced Alias Field:	First Name	
	Characters N/A - N/A	
	OK Cancel	

Figure 5.1.3.3: User Defined Aliases

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Alias Type:

A Simple Alias queries the domain controller for the Full Name field. An Advanced Alias queries an Active Directory domain controller for multiple attributes assigned to a user account. The Advanced Alias option is more powerful and retrieves more information than the Simple Alias option. However, the Advanced Alias option cannot be used in every environment.

Alias Name:

Enter a descriptive name for your alias. This name can be used throughout your configuration and will be dynamically substituted with the value retrieved from the domain controller. An Alias Name is marked for substitution by prepending it with two dollar signs. For example, if you choose fname as your Alias Name, you will use \$\$fname anywhere you want the substitution to occur.

Full Name Format:

Choose the format of the Full Name field. This option applies to Simple Aliases only.



Simple Alias Field:

The Simple Alias Fields are derived from the Full Name field. Select the field containing the values you want assigned to your Alias Name. This option applies to Simple Aliases only.

Advanced Alias Field:

The Advanced Alias Fields correspond to the fields listed in Active Directory. Select the field containing the value you want assigned to your Alias Name. This option applies to Advanced Aliases only.

Characters:

Allows you to use only part of the value retrieved from the domain controller. If you enable this option, you will need to choose a starting character and an ending character. For example, entering one (1) for the starting character and eight (8) for the ending character would retrieve the first eight (8) characters.

Example:

Filter: Global Settings Alias Type: Advanced Alias Alias Name: email Advanced Alias Field: E-mail

The above example will create an alias named **email**. This alias will contain the user's E-mail address retrieved from Active Directory. Anywhere you use **\$\$email** in your configuration, the user's E-mail address will be substituted.

Example:

Filter: Global Settings Alias Type: Simple Alias Alias Name: Iname_initial Full Name Format: First Middle Last Simple Alias Field: Last Name Characters: 1-1

The above example will create an alias named <code>lname_initial</code>. This alias will contain the first character of the user's Last Name. The user's Last Name is derived from the Full Name Format option and the Full Name value retrieved from the authenticating domain controller. Anywhere you use <code>\$\$lname_initial</code> in your configuration, the first character of the user's Last Name will be substituted.



5.1.3.4 User Defined Scripts

Administrators wishing to utilize a custom written KiXtart module will add it to their configuration here. ProfileUnity offers the option to include custom KiXtart scripts both before ProfileUnity (Pre-Execution) and after ProfileUnity (Post-Execution).

Default	User Defined Scripts - Edit
Execute: Before	ProfileUnity (Pre-Execution)
File:	
🗆 Ru	In-Process
	OK Cancel

Figure 5.1.3.4: User Defined Scripts

Execute:

Choose whether your custom KiXtart script should execute before or after ProfileUnity.

File:

Enter the full path to your KiXtart script. Surrounding quotes are automatically added to the file.

NOTE: Drives mapped by the Drive Mapping configuration module are not available. The recommended location to store your custom KiXtart scripts is in the netlogon share on your domain controller. Custom scripts stored in this location will take advantage of replication and can be included as follows: @lserver\netlogon\your script.kix.

Run In-Process:

Selecting this option will merge your custom KiXtart script into ProfileUnity. This option should only be selected if you want all or parts of your script exposed to ProfileUnity. For example, if you are utilizing a Custom Function as part of a filter, this option must be selected.

NOTE: Custom KiXtart scripts are not checked for proper syntax or function. You are encouraged to create and test your custom scripts prior to inclusion with the User Defined Scripts module.



5.1.3.5 Application Launcher

This module allows you to launch applications on your client machines during or after ProfileUnity execution.

Default		Application Launcher - Edit
Filter: Filespec: Arguments: Timing:	Global Settings	
	Hide Progress During Execution Run Asynchronously C Everyday	October • 2009 • S M T W T F S 27 28 29 30 1 2 3
Schedule:	C Weekly on Sunday C Monthly on Day 1 C Specific Date 10/27/2009	4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31
Frequency:	Every Logon	1234567
UID: Tracking Path:	N/A N/A	Today
	OK Cancel]

Figure 5.1.3.5: Application Launcher

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Filespec:

Enter the full path to the executable. Surrounding quotes are automatically added to the filespec.

NOTE: Drives mapped by the Drive Mapping configuration module are not available.

Arguments:

Enter any arguments required by the executable. Arguments are not automatically quoted.

Timing:

Choose whether your application should launch during or after ProfileUnity execution.

Hide Progress During Execution:

Selecting this option will hide the ProfileUnity progress display while your application executes. This option is not available if you enable Run Asynchronously.



Run Asynchronously:

By default, ProfileUnity waits for your application to terminate prior to continuing. When this option is selected, ProfileUnity will not wait for your application to terminate.

Schedule:

Choose the schedule your application should execute on.

Frequency:

Choose the frequency your application should execute on.

UID:

The UID is a unique identifier that is automatically generated by ProfileUnity. Normally, the UID does not need to be changed. Changing the UID will reset the execution history associated with the application. For example, if you chose a frequency of One Time (User) and you want the application to run a second time, changing the UID will cause the application to execute again. This option does not apply if you choose a Frequency of Every Logon.

Tracking Path:

The Tracking Path designates the UNC name of the network share ProfileUnity will use to store execution history. When you create the share, you will need to grant write permission to all users using ProfileUnity. If this share is unavailable or does not have write permission, ProfileUnity will not execute the application. This option does not apply if you choose a Frequency of Every Logon.

NOTE: Inside the share ProfileUnity will create a folder named after the UID of the application. Therefore, it is safe to use the same share as the Tracking Path for multiple applications. If you wish to reset the execution history for an application, you can delete the folder associated with the application's UID.

Example:

Filter: Global Settings Filespec: C:\Program Files\Adobe\Acrobat 6.0\Acrobat\Acrobat.exe Arguments: "\\ATLFS01\public\Employee Handbook.pdf" Timing: After Configuration Execution Run Asynchronously: Enabled Schedule: Everyday Frequency: One Time (User) UID: gtnj8nvrp4oe38m Tracking Path: \\ATLFS02\apptrack\$\$

The above example will launch Adobe Acrobat and open the file **Employee Handbook.pdf** one time for each user. Since Run Asynchronously has been enabled, ProfileUnity will not wait for the user to close the Acrobat reader. The Arguments passed to the Filespec have been surrounded with quotes as **Employee Handbook.pdf** contains a space.

NOTE: The share name used for the Tracking Path is **\\ATLFS02\apptrack\$**. Since \$ is a reserved character, it has been escaped with \$\$. Please see section 5.1.2.2 for assistance escaping reserved characters.



5.1.3.6 Drive Mapping

The Drive Mapping module is used to connect and disconnect network drives.

Default	Drive Mapping - Edit
Filter: Global Settings 📃	
Action: Map 💽 🗖 Disconnect Before Mapping	
Drive Letter: 🛛 A: 🔽 🗖 Map Persistent	
UNC Path:	
Explorer Label:	
OK Cancel	
Figure 5.4.9.6. Drive Menuine	

Figure 5.1.3.6: Drive Mapping

Filter:

Select the name of the filter you want assigned to this configuration element.

Action:

Choose whether you want to Map a drive, Disconnect a drive, or Disconnect All drives.

Disconnect Before Mapping:

Selecting this option will disconnect the drive before mapping it. This option only applies if you choose Map for the action.

Drive Letter:

Select the drive letter you want to Map or Disconnect. This option does not apply if you choose Disconnect All for the Action.

Map Persistent:

Persistent drive mappings are mappings that are reconnected automatically at the next logon. This option only applies if you choose Map for the action.



UNC Path:

Enter the UNC Path you want the Drive Letter mapped to. This option only applies if you choose Map for the action.

Explorer Label:

The Explorer Label is the name that will show up in My Computer and the standard Windows dialog boxes next to the drive letter. The Explorer Label can be changed on Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7 clients only. This option only applies if you choose Map for the action.

NOTE: ProfileUnity leverages Windows Scripting Host to change the Explorer Label. If you disable Windows Scripting Host on your clients, ProfileUnity will be unable to modify the Explorer Label.

Example:

Filter: Global Settings Action: Disconnect All

The above example will disconnect all drives.

Example:

Filter: Global Settings Action: Map Drive Letter: H: Map Persistent: Enabled UNC Path: \\ATLFS02\@userid Explorer Label: Home Directory

The above example leverages the macro @userid. When ProfileUnity executes, the @userid macro is expanded into the username. Therefore, the H: drive will be mapped to a per-user share located on server ATLFS02. The drive will be mapped persistent and will be assigned the label Home Directory on Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7 clients.



5.1.3.7 Environment Vars

Sets and clears environment variables. Environment variables are modified in the environment of the current user.

Default		Environment Vars - Edit
Filter:	Global Settings 📃	
Environment Variable:		
Value:		
	OK Car	ancel

Figure 5.1.3.7: Environment Vars

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Environment Variable:

Enter the name of the environment variable you want to modify. The name should not be enclosed in percent signs.

Value:

Enter the value you want assigned to the environment variable. Leaving this value blank will delete the environment variable.

Example:

Filter: Global Settings Environment Variable: MYDIR Value: C:\MyDir

The above example assigns the value C: \MyDir to the environment variable MYDIR.



5.1.3.8 Folder Redirection

Shell folders are special folders that Windows uses to indicate the default location for many types of settings and data. This module allows you to redirect shell folders to an alternate location, and optionally move or copy existing data. A common use for this module is redirecting "My Documents" to a network share.

Default		Folder Redirection - Edit
Filter:	Global Settings 💌	
Shell Folder:	Start Menu 🗖 Reset to Default	
Redirect to Folder:		
Existing Files:	Hide Previous Location After Redirection No Change	
	Only Migrate Existing Files on Primary Client Remove Extraneous Files Limit Bandwidth to N/A Kbps	
Exclude:	N/A	
	Seperate multiple entries with commas	
	OK Cancel	

Figure 5.1.3.8: Folder Redirection

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Shell Folder:

Select the Shell Folder you want to redirect.

Reset to Default:

Enabling this option will reset the selected Shell Folder to its default location.

Redirect to Folder:

Enter the path you want the Shell Folder redirected to. This option is not available if Reset to Default has been selected.

Hide Previous Location After Redirection:

Enabling this option causes ProfileUnity to set the hidden attribute on and rename the previous shell folder location after redirection.



Existing Files:

Files and folders that exist in the current Shell Folder location can optionally be copied, moved, or synchronized to the new location. Depending on the amount of data that currently exists, enabling copy or move can cause a delay during logon while the files and folders are copied or moved to the new location. Alternatively, the synchronize option will transfer the existing files and folders in the background without impacting the user's logon time. The synchronize option firsts performs a background synchronization of the user's existing files and folders. At the next logon, after the initial background synchronization has completed, foreground synchronization takes place to synchronize any missing files or folders. Once the foreground synchronization has completed the folder is then redirected. The user does have to wait for the foreground synchronization to complete during logon. However, the foreground synchronize option is usually quick whereas it is only moving a few missing files and folders. The synchronize option is the recommended method for migrating existing files and folders. This option is not available if Reset to Default has been selected.

Only Migrate Existing Files on Primary Client:

Enabling this option causes ProfileUnity to only migrate existing files on the user's Primary Client. The user's Primary Client is the first computer a user logs on to after a folder redirection is configured.

Remove Extraneous Files:

Enabling this option will delete files and folders that exist in the new location and do not exist in the current location during synchronization. This option is only available if Sync to New Location is chosen for Existing Files.

NOTE: This option can cause data loss if not used with care. It is recommended that this option be left disabled unless you have a specific need to enable it.

Limit Bandwidth to:

Enabling this option will limit the amount of bandwidth the background synchronization process consumes. This option is only available if Sync to New Location is chosen for Existing Files.

Exclude:

Paths entered will be excluded from the background synchronization process. This option is only available if Sync to New Location is chosen for Existing Files. The following matching rules apply:

- a leading '\' anchors the match to the full path only (otherwise partial matches occur)
- a '*' matches any path component except a backslash
- a '?' matches any character except a backslash
- a trailing '\' limits the match to directories and not files

Example:

Filter: Global Settings Shell Folder: Personal (My Documents) Reset to Default: Disabled Redirect to Folder: H:\My Documents Existing Files: Copy to New Location

The above example redirects the My Documents Shell Folder to H: \My Documents. All existing files and folders are copied to the new location.

NOTE: This example assumes the H: drive is mapped to a network share. It is also possible to use a UNC path for the Redirect to Folder.



5.1.3.9 INI Files

Many programs rely on INI files for their configuration. This module enables ProfileUnity to manipulate INI files during user logon.

Default		INI Files - Edit
Filter:	Global Settings	
Action:	Write Value	
Filespec:		
Section:		
Value:		
Data:		
	OK Cancel	

Figure 5.1.3.9: INI Files

The structure of an INI file is shown in figure 5.1.3.9.1.

[Section] Value=Data

Figure 5.1.3.9.1: INI File Structure

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Action:

Select one of the following actions:

- Write Value Modifies or creates a value and assigns data to it.
- Delete Value Deletes a value and associated data.
- Delete Section Deletes an entire section.

Filespec:

Enter the full path to the INI file. If this parameter does not include a full path, ProfileUnity searches for the file in the Windows directory.

Section:

Enter the name of the section to be modified in the INI file. If the section does not exist, it is created. The section name is not case-sensitive, and can contain any combination of uppercase and lowercase letters.

Value:

Enter the name of the value to be modified in the INI file. If the value does not exist, it is created. This option is not available if Delete Section is selected as the Action.



Data:

Enter the data you want assigned to the value. This option is only available if Write Value is selected as the Action.

Example:

Filter: Global Settings Action: Write Value Filespec: %APPDATA%\ICAClient\pn.ini Section: ENTRIGUE Value: HttpBrowserAddress Data: ica.entrigue.net

The above example demonstrates using the INI Files module to update Citrix Program Neighborhood settings. The HttpBrowserAddress for the application set named ENTRIGUE will be set to ica.entrigue.net. The pn.ini file will have the changes made to it shown in figure 5.1.3.9.2.

[ENTRIGUE] HttpBrowserAddress=ica.entrigue.net

Figure 5.1.3.9.2: pn.ini Changes

NOTE: The **APPDATA** environment variable only exists by default on Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7 clients. You can use the Environment Vars module to set this variable on clients running other operating systems.



5.1.3.10 Internet Explorer

This module is used to configure Internet Explorer features such as Start Page, Download Directory, and Favorites. This module supports Internet Explorer versions 4.0 and higher.

Default		Internet Explorer - Edit
Filter:	Global Settings	
Start Page:		
Download Dir:		
	No Change 💌 Personalized Favorites Menu	
	Sort Favorites by Name	
	🔲 Remove Internet Connection Wizard	
	OK Cancel	

Figure 5.1.3.10: Internet Explorer

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Start Page:

Enter the URL of the page you want Internet Explorer to display on startup. If you want Internet Explorer to start with a blank page, enter about:blank for the Start Page.

Download Dir:

The Download Dir is the location presented to the user when asked to save a file downloaded with Internet Explorer. Enter the full path to the folder you want to use.

Personalized Favorites Menu:

On clients running Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7, the favorites menu is automatically updated to keep the favorites you use most often at the top of the menu where they are usually more accessible. This option allows you to control the Personalized Favorites Menu setting used by your users. Available choices are: Enable, Disable, and No Change.

Sort Favorites by Name:

Selecting this option will sort the Internet Explorer Favorites menu alphabetically. This option is only available on Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7.

Remove Internet Connection Wizard:

Selecting this option will disable the Internet Connection Wizard and remove the Internet Connection Wizard desktop shortcut.



Example: Filter: Global Settings Start Page: http://www.entrigue.net Download Dir: C:\Temp Personalized Favorites Menu: Disable Sort Favorites by Name: Not Selected Remove Internet Connection Wizard: Selected

The above example sets the Internet Explorer start page to http://www.entrigue.net, sets the download directory to C:\Temp, disables Personalized Favorites, and removes the Internet Connection Wizard.



5.1.3.11 Internet Proxy

This module is used to adjust Internet Explorer's proxy settings to match your network configuration. This module supports Internet Explorer versions 4.0 and higher.

Default	Internet Proxy - Edit
Filter: Global Settings	
Automatically Detect Settings	
Use Automatic Configuration Script	
Address: N/A	
Use a Proxy Server	
Address: N/A	
Port: N/A	
Bypass Proxy Server for Local Addresses	
Do Not Use Proxy Server for Addresses Beginning With:	
N/A	
Use semicolons (;) to seperate entries.	
OK Creat	

Figure 5.1.3.11: Internet Proxy

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Automatically Detect Settings:

Selecting this option enables Internet Explorer's automatic proxy detection feature. This option is only available on Internet Explorer versions 5.0 and higher.

Use Automatic Configuration Script:

Select this option if you want to configure Internet Explorer proxy settings with a configuration script. You will need to enter the complete path to the configuration script in the **Address** field.

Use a Proxy Server:

Selecting this option instructs Internet Explorer to connect to the Internet by using the proxy server settings you specify in the **Address** and **Port** fields.

NOTE: You can configure Internet Explorer to use different proxy servers for different protocols by leaving the Port field blank and using the following format for the Address field: protocol=address:port. The available protocols are ftp, gopher, http, https, and socks. You will need to separate multiple entries with semicolons. For example: http=proxy1.company.com:8000;ftp=proxy2.company.com:3128.



Bypass Proxy Server for Local Addresses:

This option instructs Internet Explorer to bypass the configured proxy settings for local addresses. This option is only available if Use a Proxy Server has been selected.

Do Not Use Proxy Server for Addresses Beginning With:

Enter addresses that Internet Explorer should access without using the configured proxy settings. This option is only available if Use a Proxy Server has been selected.

NOTE: You can use wildcards to match addresses. For example: *.xyz.com, 192.168.*.

Example:

Filter: Global Settings Automatically Detect Settings: Not Selected Use Automatic Configuration Script: Not Selected Use a Proxy Server: Selected Address: proxy.entrigue.net Port: 8000 Bypass Proxy Server for Local Addresses: Selected Do Not Use Proxy Server for Addresses Beginning With: *.entrigue.net

The above example configures Internet Explorer to use proxy server **proxy.entrigue.net** on port 8000. The proxy server will not be used for local addresses or for addresses in the **entrigue.net** domain.



5.1.3.12 Inventory

This module creates a report listing computer name, computer domain membership, username, processor, memory, display resolution, MAC address, IP address, operating system, Internet Explorer version, and installed applications. The report also lists the service pack version and installed hotfixes.

Default	I	nventory - Edit
Filter:	Global Settings	
Action:	Upload XML File	
Upload Path:		
Server URL:	N/A	
Transaction Key:	N/A	
	OK Cancel	

Figure 5.1.3.12: Inventory

NOTE: On systems with more than 4GB of RAM, memory is reported incorrectly. On systems with more than one IP address, only the first IP address is listed. Applications must be listed in "Add or Remove Programs" to be included in the report.

Filter:

Select the name of the filter you want assigned to this configuration element.

Action:

Choose whether you want to Upload XML File or Use Reporting Server.

Upload Path:

The Upload Path designates the UNC name of the network share ProfileUnity will use to store the generated report in XML format. When you create the share, you will need to grant write permission to all users using ProfileUnity. If this share is unavailable or does not have write permission, ProfileUnity will not create the report. This option only applies if you choose Upload XML File for the action.

NOTE: Inside the share ProfileUnity will create an XML file named "computer name.xml" for each client machine that executes this module.

Server URL:

The Server URL is the address of the machine running the ProfileUnity Management Console. The URL can either be a fully qualified domain name or an IP address. This option only applies if you choose Use Reporting Server for the action.

Transaction Key:

The Transaction Key is a shared secret used to authenticate the connection between the client and the reporting server. This option only applies if you choose Use Reporting Server for the action.

Example:



Filter: Global Settings Action: Use Reporting Server Server URL: https://ssv2.entrigue.net Transaction Key: mvpntw2pcrvntmp

The above example will send inventory reports to the ProfileUnity Management Console located at https://ssv2.entrigue.net. The connection will be made using SSL and authenticated with shared secret mvpntw2pcrvntmp.

Example: Filter: Global Settings Action: Upload XML File Upload Path: \\ATLFS02\inventory\$\$

The above example will create reports in XML format on the network share \\ATLFS02\inventory\$.

NOTE: The share name used for the Upload Path is **\\ATLFS02\inventory\$**. Since \$ is a reserved character, it has been escaped with \$\$.



5.1.3.13 MAPI Profiles

This module is used to configure Windows Messaging subsystem profiles for access to Microsoft Exchange server. The Windows Messaging subsystem is used by Microsoft Outlook to communicate with Microsoft Exchange. This module supports all versions of Outlook. Outlook 98 and Outlook 2000 must be in corporate mode.

Default		MAPI Profiles - Edit
Filter:	Global Settings	
Action:	Create Profile	
Mail Profile Name:		
Exchange Server:		
Mailbox Name:		
	Enable Personal Address Book	
	PAB Location: N/A	
	Enable Personal Folders	
	PST Location: N/A	
	Enable Offline Folders	
	OST Location: N/A	
	Enable Offline Address Book	
	OAB Path: N/A	
	Set as Default Profile	
	OK Cancel	

Figure 5.1.3.13: MAPI Profiles

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Action:

Select one of the following actions:

- Create Profile
- Create Only if No Profiles Exist
- Create Only if No Profile Exists with this Name
- Delete Profile
- Delete All Profiles
- Delete All Profiles Except Default Profile



Mail Profile Name:

Enter the name of the mail profile. This option is not available if Delete All Profiles or Delete All Profiles - Except Default Profile is selected as the Action.

Exchange Server:

Enter the name of the Exchange Server. This option is only available if Create Profile, Create -Only if No Profiles Exist, or Create - Only if No Profile Exists with this Name is selected as the Action.

NOTE: Outlook XP and Outlook 2003 will hang during logon if the exchange server is not valid or available.

Mailbox Name:

Enter the name of the mailbox. This option is only available if Create Profile, Create - Only if No Profiles Exist, or Create - Only if No Profile Exists with this Name is selected as the Action.

Enable Personal Address Book:

Selecting this option will configure the mail profile to use a personal address book. You will need to enter the complete path to the personal address book in the **PAB Location** field. This option is only available if Create Profile, Create - Only if No Profiles Exist, or Create - Only if No Profile Exists with this Name is selected as the Action.

Enable Personal Folders:

Selecting this option will configure the mail profile to use personal folders. You will need to enter the complete path to the personal folder file in the **PST Location** field. This option is only available if Create Profile, Create - Only if No Profiles Exist, or Create - Only if No Profile Exists with this Name is selected as the Action.

Enable Offline Folders:

Selecting this option will configure the mail profile to use offline folders. You will need to enter the complete path to the offline folder file in the **OST Location** field. This option is only available if Create Profile, Create - Only if No Profiles Exist, or Create - Only if No Profile Exists with this Name is selected as the Action.

NOTE: If the offline folder file specified in **OST Location** currently exists, it will be deleted. Offline folders are not supported on Terminal Servers.

Enable Offline Address Book:

Selecting this option will configure the mail profile to use an offline address book. You will need to enter the complete path to the offline address book in the **OAB Location** field. This option is only available if Create Profile, Create - Only if No Profiles Exist, or Create - Only if No Profile Exists with this Name is selected as the Action.

Set as Default Profile:

Selecting this option will configure the mail profile as the default profile.



Example: Filter: Global Settings Action: Create - Only if No Profiles Exist Mail Profile Name: ENTRIGUE Exchange Server: ATLEX01 Mailbox Name: @userid Enable Personal Address Book: Selected PAB Location: H:\mail.pab Enable Personal Folders: Not Selected Enable Offline Folders: Not Selected Enable Offline Address Book: Not Selected Set as Default Profile: Selected

The above example will create a mail profile named **ENTRIGUE** only if no profiles currently exist. This example leverages the macro @userid. When ProfileUnity executes, the @userid macro is expanded into the username. Therefore, the above example will create a mail profile that connects to each user's mailbox on the exchange server named **ATLEX01**. The mail profile will be configured to use **H**: \mail.pab as a personal address book and will be set as the default profile.

NOTE: Please see section 5.1.2.4 for further assistance with macros.



5.1.3.14 Message Boxes

This module allows you to display popup messages to your users during logon.

Default			Message Boxes - Edit
Filter:	Global Settings		
Window Title:			
Message:			
Style:	Informational 💌		7
Timeout:	0	October - 2009 -	
Schedule:	C Everyday C Weekly on Sunday C Monthly on Day 1 Specific Date 10/27/2009	S M I W I F S 27 28 29 30 1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31	
Frequency:	Every Logon 💽	1234567	
UID:	N/A	<u>Today</u>	
Tracking Path:	N/A		
	OK Cancel	J	

Figure 5.1.3.14: Message Boxes

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Window Title:

Enter the text you want displayed as the message box title.

Message:

Enter the text you want displayed in the message box.

Style:

This parameter defines the style of the message box.



Timeout:

You can configure message boxes to wait for user acknowledgement or to close automatically after a specified amount of time elapses. This parameter represents the number of seconds after which to close the message box. If you do not want the message box to automatically close, enter 0 seconds.

Schedule:

Choose the schedule your message box should display on.

Frequency:

Choose the frequency your message box should display on.

UID:

The UID is a unique identifier that is automatically generated by ProfileUnity. Normally, the UID does not need to be changed. Changing the UID will reset the display history associated with the message box. For example, if you chose a frequency of One Time (User) and you want the message box to display a second time, changing the UID will cause the message box to display again. This option does not apply if you choose a Frequency of Every Logon.

Tracking Path:

The Tracking Path designates the UNC name of the network share ProfileUnity will use to store display history. When you create the share, you will need to grant write permission to all users using ProfileUnity. If this share is unavailable or does not have write permission, ProfileUnity will not display the message box. This option does not apply if you choose a Frequency of Every Logon.

NOTE: Inside the share ProfileUnity will create a folder named after the UID of the message box. Therefore, it is safe to use the same share as the Tracking Path for multiple message boxes. If you wish to reset the execution history for a message box, you can delete the folder associated with the message box's UID.

Example:

Filter: Global Settings Window Title: Weekly Staff Meeting Reminder Message: The weekly staff meeting is scheduled to take place at 1:30PM in the conference room. Style: Informational Timeout: 10 Schedule: Weekly on Monday Frequency: Every Logon

The above example will display the message box titled **Weekly Staff Meeting Reminder** every Monday at every logon. If the user fails to acknowledge the message box, it will automatically close after being displayed for **10** seconds.



5.1.3.15 Microsoft Shared Fax

This module is used to specify sender information for the Microsoft Fax Client. This module supports the fax client included with Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7.

Default		Microsoft Shared Fax - Edit
Filter:	Global Settings	
Field:	Full Name	
Value:]
	OK Cancel	

Figure 5.1.3.15: Microsoft Shared Fax

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Field:

Select the field you want to modify. All fields other than Receipt E-Mail are used to specify sender information and correspond to the fields shown in figure 5.1.3.15.1.

Sender Informati	on ?X
5pecify	sender information to be included on cover pages.
Full <u>n</u> ame:	
Eax number:	
<u>E</u> -mail:	
<u>T</u> itle:	Company:
Office location:	Department:
Home phone:	Work phone:
<u>A</u> ddress:	×
<u>B</u> illing code:	
	OK Cancel

Figure 5.1.3.15.1: Sender Information


The Receipt E-Mail field is used for delivery notification as shown in figure 5.1.3.15.2.

Send Fax Wizard		×
Delivery Notification Specify how to be notified on the completion of a fax delivery.		
How do you want to be notified of a successful or failed fax deliv	/ery?	
🔿 <u>D</u> on't notify		
C Pop up a message on this machine		
E-mail message Receipt E-Mail	Address Book	
 Single receipt for multiple recipients transmission Attach copy of sent fax 		
< <u>B</u> ack	<u>N</u> ext >	Cancel

Figure 5.1.3.15.2: Receipt E-Mail

NOTE: Using ProfileUnity to modify any Field will disable the wizard that is presented to the user on first use of the fax client.

Value:

Enter the value you want assigned to the Field.

NOTE: You can remove existing data from a Field by leaving the Value blank.

Example: Filter: Global Settings Field: Full Name Value: @fullname

The above example leverages the macro <code>@fullname</code>. When ProfileUnity executes, the <code>@fullname</code> macro is expanded into the user's full name. Therefore, the sender <code>Full Name</code> field will be set to the user's full name.

NOTE: Please see section 5.1.2.4 for further assistance with macros.



5.1.3.16 Office File Locations

This module allows you to modify the default file locations for Microsoft Office.

Default				Offi	ce File Locations - Edit
Filter:	Global Settings	-			
Version:	Auto Detect 💌				
Folder:	Word Save Folder		•		
Location:					
		OK	Cancel		

Figure 5.1.3.16: Office File Locations

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Version:

Select the version of Office you want to modify. The recommended setting is Auto Detect. However, if you want to specify different locations for different versions of Office, you will need to specify the version you want to modify.

Folder:

Select one of the following folders:

- Word Save Folder Supports Word 95 and Newer.
- Word Clip Art Folder Supports Word 95 and Newer.
- Word Tools Folder Supports Word 95 and Newer.
- Word AutoRecovery Folder Supports Word 95 and Newer.
- Word Startup Folder Supports Word 95 and Newer.
- Excel Save Folder Supports Excel 95 and Newer.
- Excel Alternate Startup Folder Supports Excel 95 and Newer.
- Power Point Save Folder Supports Power Point 95 and Newer.
- Access Save Folder Supports Access 97 and Newer.
- Visio Save Folder Supports Visio 2000 and Newer.
- Publisher Publications Folder Supports Publisher 2003 and Newer.
- Publisher Pictures Folder Supports Publisher 2003 and Newer.
- Office Templates Folder Supports Office 95 and Newer.
- Office Shared Templates Folder Supports Office 95 and Newer.

Location:

Enter the full path to the location the Folder should default to.



Example: Filter: Global Settings Version: Auto Detect Folder: Word Save Folder Location: H:\Documents

The above example will redirect the **Word Save Folder** to **H**: \Documents. Since Auto Detect has been selected, all installed versions of Word will be modified.



5.1.3.17 Office Options

This module allows you to configure Office user information and set options that control interaction with the user.

Filter: Global Settings User Name:	Default		Office Options - Edit
Filter: Global Settings User Name:			
Hiter: Global Settings User Name: User Name: Initials: Initials: No Change No Change No Change No Change No Change No Change User Name: No Change Startup Dialogs No Change No Change User Name: No Change User Show Office Clipboard Automatically No Change No Change User Name: No Change Show Office Clipboard Icon on Taskbar No Change Show Status Near Taskbar When Copying	Filtern	Clobal Settings	
User Name: Initials: No Change Personalized Menus No Change Startup Dialogs No Change Customer Feedback No Change Language Bar No Change Show Office Clipboard Automatically No Change Collect Without Showing Office Clipboard No Change Show Office Clipboard Icon on Taskbar No Change Show Status Near Taskbar When Copying	Filter;		
Initials: No Change Personalized Menus No Change Startup Dialogs No Change Customer Feedback No Change Language Bar No Change Show Office Clipboard Automatically No Change Collect Without Showing Office Clipboard No Change Show Office Clipboard Icon on Taskbar No Change Show Status Near Taskbar When Copying	User Name:		
No Change Personalized Menus No Change Startup Dialogs No Change Customer Feedback No Change Language Bar No Change Show Office Clipboard Automatically No Change Collect Without Showing Office Clipboard No Change Show Office Clipboard Icon on Taskbar No Change Show Status Near Taskbar When Copying	Initials:		
No Change Startup Dialogs No Change Customer Feedback No Change Language Bar No Change Show Office Clipboard Automatically No Change Collect Without Showing Office Clipboard No Change Show Office Clipboard Icon on Taskbar No Change Show Status Near Taskbar When Copying		No Change 💌 Personalized Menus	
No Change Customer Feedback No Change Language Bar No Change Show Office Clipboard Automatically No Change Collect Without Showing Office Clipboard No Change Collect Without Showing Office Clipboard No Change Show Office Clipboard Icon on Taskbar No Change Show Status Near Taskbar When Copying		No Change 💌 Startup Dialogs	
No Change Language Bar No Change Show Office Clipboard Automatically No Change Collect Without Showing Office Clipboard No Change Show Office Clipboard Icon on Taskbar No Change Show Status Near Taskbar When Copying		No Change 💌 Customer Feedback	
No Change Show Office Clipboard Automatically No Change Collect Without Showing Office Clipboard No Change Show Office Clipboard Icon on Taskbar No Change Show Status Near Taskbar When Copying		No Change 💌 Language Bar	
No Change 💽 Collect Without Showing Office Clipboard No Change 💌 Show Office Clipboard Icon on Taskbar No Change 💌 Show Status Near Taskbar When Copying		No Change 💌 Show Office Clipboard Automatically	
No Change 💌 Show Office Clipboard Icon on Taskbar No Change 💌 Show Status Near Taskbar When Copying		No Change 💽 Collect Without Showing Office Clipboard	ł
No Change 💌 Show Status Near Taskbar When Copying		No Change 💌 Show Office Clipboard Icon on Taskbar	
		No Change 💌 Show Status Near Taskbar When Copyin	ıg
OK Cancel		OK Cancel	

Figure 5.1.3.17: Office Options

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

User Name:

Enter the user name Office should use. This option supports Office 97 and newer versions.

Initials:

Enter the initials Office should use. This option supports Office 97 and newer versions.

Personalized Menus:

Office 2000, Office XP, Office 2003, and Office 2007 automatically update menus to keep the features you use most often at the top of the menu where they are usually more accessible. This option allows you to control the Personalized Menus setting used by your users. Available choices are: Enable, Disable, and No Change.

Startup Dialogs:

This option allows you to control the Getting Started task pane that displays when an Office application is started. Available choices are: Enable, Disable, and No Change. This option supports the following applications from the Office XP and Office 2003 suites: Access, Excel, Power Point, Word, FrontPage, and Visio. Additionally, this option supports Publisher 2003.



Customer Feedback:

This option controls whether Microsoft is allowed to collect anonymous usage statistics about the way you use Office. Available choices are: Enable, Disable, and No Change. This option supports Office 2003 and newer versions.

Language Bar:

This option controls display of the Language Bar on the user desktop. Available choices are: Enable, Disable, and No Change. This option supports Office XP and newer versions.

Show Office Clipboard Automatically:

This option controls automatic display of the Office clipboard when copying items. Available choices are: Enable, Disable, and No Change. This option supports Office 2000 and newer versions.

Collect Without Showing Office Clipboard:

This option allows items to be copied to the Office clipboard without displaying the Office clipboard. Available choices are: Enable, Disable, and No Change. This option supports Office XP and newer versions.

Show Office Clipboard Icon on Taskbar:

This option controls display of the Office clipboard icon in the system tray when the Office clipboard is active. Available choices are: Enable, Disable, and No Change. This option supports Office XP and newer versions.

Show Status Near Taskbar When Copying:

This option controls display of the collected item message when copying items to the Office clipboard. Available choices are: Enable, Disable, and No Change. This option supports Office XP and newer versions.

Example:

Filter: Global Settings User Name: @fullname Initials: \$\$first_initial\$\$last_initial Personalized Menus: Disable Startup Dialogs: Disable Customer Feedback: Disable Language Bar: Disable Show Office Clipboard Automatically: Disable Collect Without Showing Office Clipboard: Enable Show Office Clipboard Icon on Taskbar: Disable Show Status Near Taskbar When Copying: Enable

The above example leverages the macro <code>@fullname</code> and the User Defined Aliases module. When ProfileUnity executes, the <code>@fullname</code> macro is expanded into the user's full name. The <code>\$\$first_initial</code> and <code>\$\$last_initial</code> are User Defined Aliases that expand into the user's first initial and last initial respectively. Therefore, the Office <code>User Name</code> field will be set to the user's full name and the Office <code>Initials</code> field will be set to the user's first initial and last initial. Collect Without Showing Office Clipboard and Show Status Near Taskbar When Copying will be enabled. All other available options will be disabled.

NOTE: Please see section 5.1.2.4 for further assistance with macros. Please see section 5.1.3.3 for further assistance with User Defined Aliases.



5.1.3.18 Outlook

This module allows you to modify settings that control Outlook behavior for message handling, message format, and AutoArchive.

Default		Outlook - Edit
Filter:	Global Settings	
	No Change 💌 Warn Before Permanently Deleting Items	
	No Change 토 Empty the Deleted Items folder on exit	
	No Change 토 Remove extra line breaks in plain text messages	
	No Change 토 Save copies of messages in Sent Items folder	
	No Change 🖃 AutoSave unsent every N/A minutes	
	No Change 🔽 Message Format	
	No Change 🔽 Use Microsoft Word as editor	
	No Change 🔽 Prompt for a profile to be used	
	No Change - AutoArchive Every N/A Days	
	Promot before AutoArchive runs	
	Delete expired items (e-mail folders only)	
	Show archive folder in folder list	
	Clean out items older than 👔 🔽 Months 💌	
	AutoArchive Path and Filename:	
	N/A	
	OK Cancel	

Figure 5.1.3.18: Outlook

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Warn Before Permanently Deleting Items:

This option controls the display of a warning message prior to deleting items. Available choices are: Enable, Disable, and No Change.

Empty the Deleted Items folder on exit:

When this option is enabled, Outlook will delete items in the Deleted Items folder when closed. Available choices are: Always, Never, On Sun, On Mon, On Tues, On Wed, On Thur, On Fri, On Sat, and No Change.



Remove extra line breaks in plain text messages:

When this option is enabled, Outlook will remove extra line breaks in plain text messages. Available choices are: Enable, Disable, and No Change. This option supports Outlook XP and newer versions.

Save copies of messages in Sent Items folder:

When this option is enabled, Outlook will save copies of sent messages in the Sent Items folder. Available choices are: Enable, Disable, and No Change.

AutoSave unsent every ____ minutes:

This option controls when Outlook saves unsent items. Available choices are: Enable, Disable, and No Change. If you enable this option, you will need to specify the number of minutes.

Message Format:

This option controls message format used by Outlook. Available choices are: HTML, Rich Text, Plain Text, and No Change.

Use Microsoft Word as editor:

When this option is enabled, Outlook will use Microsoft Word as the message editor. Available choices are: Enable, Disable, and No Change. This option supports all Outlook versions except Outlook 2007.

NOTE: Outlook 98 Only - Enabling this option overrides the message format used. Disabling this option will set the Message Format to Rich Text if Message Format is set to No Change.

Prompt for a profile to be used:

When this option is enabled, Outlook will prompt the user to choose a profile on startup. Available choices are: Enable, Disable, and No Change.

AutoArchive Every ____ Days:

This option controls when Outlook AutoArchives items. Available choices are: Enable, Disable, and No Change. If you enable this option, you will need to specify the number of days.

Prompt before AutoArchive runs:

When this option is selected, the user will be notified prior to Outlook AutoArchiving items.

Delete expired items (e-mail folders only):

When this option is selected, Outlook will delete expired items instead of archiving them when AutoArchive runs.

NOTE: If you select this option, items will be permanently deleted, not archived.

Show archive folder in folder list:

When this option is selected, the AutoArchive file will be displayed in the Outlook folder list. This option supports Outlook XP and newer versions.

Clean out items older than:

This option specifies the default time period Outlook uses when AutoArchiving. Items older than this time period will be AutoArchived. This option supports Outlook XP and newer versions.

AutoArchive Path and Filename:

Enter the full path to the AutoArchive file. If you leave this option blank, Outlook will use the user's currently configured AutoArchive file.



Example: Filter: Global Settings Warn Before Permanently Deleting Items: Enable Empty the Deleted Items folder on exit: On Fri Remove extra line breaks in plain text messages: Disable Save copies of messages in Sent Items folder: Enable AutoSave unsent every ____ minutes: Enable 5 Message Format: Rich Text Use Microsoft Word as editor: Disable Prompt for a profile to be used: Disable AutoArchive Every ___ Days: No Change

The above example enables Warn Before Permanently Deleting Items and Save copies of messages in Sent Items folder. Every Friday, Outlook will be configured to Empty the Deleted Items folder on exit. Additionally, Outlook will AutoSave unsent messages every 5 minutes and messages will be composed in **Rich Text** format. The user's current AutoArchive settings will be preserved. All other available options will be disabled.



5.1.3.19 Outlook Express

This module allows you to create and delete accounts for POP3, IMAP, NNTP, and LDAP in Outlook Express. This module supports Outlook Express versions 5.0 and newer.

Default	Outlook Express - Edit
Filter: Global Settings	
Account Type: Mail (POP3)	
Action: Create Account	
Account Name:	
User Display Name:	
E-Mail Address:	
Server: Port: 110 🗖 Enable SSL	
Server Requires Login	
Login Name:	
SMTP Server: Port: 25 Enable SSL	
Lise Mail Server Login	
SMTP Login Name: N/A	
Root Folder Path: N/A	
Search Base: N/A	
Leave a Copy of Messages on Server	
Check Names Against when Sending Mail	
Set as Default Account	
OK Cancel	

Figure 5.1.3.19: Outlook Express

Outlook Express versions 5.0 and newer support multiple identities. Simply stated, an identity is a logical container that holds account settings. ProfileUnity creates and deletes account settings held in the default identity only. If you are using Outlook Express version 5.0, please see figure 5.1.3.19.1 for assistance setting the default identity. If you are using Outlook Express version 5.5 or newer, please see figure 5.1.3.19.2.



Manage	Identities	<u>? ×</u>
<u>■0</u> 22	Click New to add a new identity. Selec and click Properties to modify the identi to delete the identity from the computer.	t an identity name ty, or click Remove
Identity r	names:	
(Main Id	dentity (Default)	<u>N</u> ew
		<u>R</u> emove
		<u>P</u> roperties
		<u>M</u> ake Default
<u>S</u> tart up	using: Main Identity (Default)	_
		Close

Figure 5.1.3.19.1: Outlook Express 5.0 Default Identity

Manage	Identities	? ×
	To add a new identity, click New. To modi select it, and then click Properties. To dele select it, and then click Remove	fy an identity, ete an identity,
<u>I</u> dentitie	s:	
Main Id	entity	New
		<u>R</u> emove
		Properties
🔽 Use	this identity when starting a program	
Mai	n Identity 🔽	
Use iden	this identity when a program cannot ask yo tity	u to choose an
Mai	n Identity	
		Close

Figure 5.1.3.19.2: Outlook Express 5.5+ Default Identity

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.



Account Type:

Select one of the following account types:

- Mail (POP3)
- Mail (IMAP)
- News (NNTP)
- Directory Service (LDAP)

Action:

Select one of the following actions:

- Create Account
- Create Only if No Accounts Exist
- Create Only if No Account Exists with this Name
- Delete Account
- Delete All Accounts
- Delete All Accounts Except Default Account

NOTE: The Outlook Express account creation wizard is disabled when ProfileUnity is used to create an account.

Account Name:

Enter a descriptive name for the account. This option is not available if Delete All Accounts or Delete All Accounts - Except Default Account is selected as the Action.

NOTE: The account name must be unique across all accounts. For example, if you create a mail account named MYCORP, you can not assign the account name MYCORP to any other account.

User Display Name:

Enter the user display name Outlook Express should use. This option is only available when creating Mail (POP3), Mail (IMAP), and News (NNTP) accounts.

E-Mail Address:

Enter the e-mail address Outlook Express should use. This option is only available when creating Mail (POP3), Mail (IMAP), and News (NNTP) accounts.

Server:

Enter the server name Outlook Express should use. This option is only available when creating accounts. You can also change the Port and Enable SSL.

Server Requires Login:

When creating News (NNTP) and Directory Service (LDAP) accounts, selecting this option allows you to specify a Login Name for the server. This option is automatically selected when creating Mail (POP3) and Mail (IMAP) accounts.

NOTE: All account types with the exception of Directory Service (LDAP) accounts will prompt the user for the password.

Login Name:

Enter the login name Outlook Express should use. When creating Mail (POP3) and Mail (IMAP) accounts, this is a required field. When creating News (NNTP) and Directory Service (LDAP) accounts, this field is required if Server Requires Login has been selected.



SMTP Server:

Enter the SMTP server name Outlook Express should use. This option is only available when creating Mail (POP3) and Mail (IMAP) accounts. You can also change the Port and Enable SSL.

SMTP Server Requires Login:

When creating Mail (POP3) and Mail (IMAP) accounts, selecting this option allows you to specify a Login Name for the SMTP server.

Use Mail Server Login:

Selecting this option instructs Outlook Express to use the Login Name as the SMTP Login Name. This option is only available when creating Mail (POP3) and Mail (IMAP) accounts if SMTP Server Requires Login is selected.

SMTP Login Name:

Enter the SMTP login name Outlook Express should use. When creating Mail (POP3) and Mail (IMAP) accounts, this is a required field if SMTP Server Requires Login is selected and Use Mail Server Login is not selected.

Root Folder Path:

Enter the root folder path Outlook Express should use. This option is only available when creating Mail (IMAP) accounts.

Search Base:

Enter the search base Outlook Express should use. This option is only available when creating Directory Service (LDAP) accounts.

Leave a Copy of Messages on Server:

When creating Mail (POP3) accounts, this option instructs Outlook Express to leave mail on the server.

Check Names Against when Sending Mail:

When creating Directory Service (LDAP) accounts, this option instructs Outlook Express to check recipient addresses against the LDAP server.

Set as Default Account:

Selecting this option sets the account as the default. This option is only available when creating accounts.



Example: Filter: Global Settings Account Type: Mail (POP3) Action: Create - Only if No Account Exists with this Name Account Name: MyCorp Mail User Display Name: @fullname E-Mail Address: \$\$email address Server: mail05.corp.com Port: 995 Enable SSL: Selected Login Name: @userid SMTP Server: smtp.corp.com Port: 25 Enable SSL: Not Selected SMTP Server Requires Login: Not Selected Leave a Copy of Messages on Server: Not Selected Set as Default Account: Selected

The above example will create a POP3 mail account named MyCorp Mail only if no account named MyCorp Mail exists. This example leverages the macros @fullname and @userid. When ProfileUnity executes, the @fullname macro is expanded into the user's full name and the @userid macro is expanded into the user's logon name. The \$\$email_address variable is a User Defined Alias that retrieves the user's e-mail address from Active Directory. Therefore, the user display name will be set to the user's full name, the e-mail address will be set to the user's email address retrieved from Active Directory, the server will be set to mail05.corp.com on port 995 with SSL enabled, the login name will be set to the user's logon name, the SMTP server will be set to smtp.corp.com on port 25, and the created account will be set as the default.

NOTE: Please see section 5.1.2.4 for further assistance with macros. Please see section 5.1.3.3 for further assistance with User Defined Aliases.



5.1.3.20 Path

This module allows you to make modifications to the search path. The path is modified in the environment of the current user.

Default		Path - Edit
Filter: Global S	ettings 🔄	
Action: Append	•	
Path:		
	OK Cancel	

Figure 5.1.3.20: Path

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Action:

Select one of the following actions:

- Append Adds to the current path
- Overwrite Replaces the current path

NOTE: The append action checks if the new path is already part of the configured path prior to adding it.

Path:

Enter the path you want to append or replace the configured path with. Surrounding quotes are automatically added to the path.

Example: Filter: Global Settings Action: Append Path: C:\Program Files\Tools

The above example will append C:\Program Files\Tools to the configured path.



5.1.3.21 Printers

This module allows you to connect and disconnect network printers. Options include capturing a port, setting the printer as default, and automatically adding the printer.

Default		Printers - Edit
Filter:	Global Settings	
Action:	Connect	
Shared Printer:		
Capture Port:	•	
V	Auto Add	
	Set as Default	
F	Do Not Set as Default if Client has Local Printer Set as Default	
Г	Do Not Capture Port if Client has Local Printer on Port	
	OK Cancel	

Figure 5.1.3.21: Printers

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Action:

Select one of the following actions:

- Connect Installs a network printer connection / captures a port.
- Disconnect Removes a network printer connection / disconnects a port.
- Disconnect All Removes all network printer connections and disconnects LPT ports 1-9.

Shared Printer:

Enter the UNC name of the shared printer. This option is not available if Disconnect All is selected as the Action.

NOTE: When Disconnect is selected as the Action, the server name portion of the UNC name must match the server name used when the printer was connected. For example, if the printer was connected with the UNC name \\psvr.company.com\hplj, you cannot use the UNC name \\psvr\hplj for the Disconnect Action.

Capture Port:

Select the port you want to capture or disconnect. This option is not available if Disconnect All is selected as the Action.



Auto Add:

Selecting this option will automatically install the printer on Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7 clients. This option is only available if Connect is selected as the Action.

NOTE: This option leverages Microsoft Point and Print technology. The printer and drivers must be properly configured on the server for this option to function. The easiest way to test Point and Print is to attempt connecting to the printer from a client. If a client machine can connect without prompting for drivers, Point and Print is properly configured.

Set as Default:

Selecting this option will set the printer as the default. This option is only available if Connect is selected as the Action and Auto Add is selected.

Do Not Set as Default if Client has Local Printer Set as Default:

Selecting this option will prevent the printer from being set as the default if the client system has a local printer configured as the default. This option is only available if Connect is selected as the Action and Set as Default is selected.

Do Not Capture Port if Client has Local Printer on Port:

Selecting this option will prevent the port from being captured if the client system has a local printer installed on the port. This option is only available if Connect is selected as the Action and a Capture Port has been selected.

Example:

Filter: Global Settings Action: Connect Shared Printer: \\PSVR\NYCP07 Capture Port: LPT1: Auto Add: Selected Set as Default: Selected Do Not Set as Default if Client has Local Printer Set as Default: Not Selected Do Not Capture Port if Client has Local Printer on Port: Not Selected

The above example will redirect the LPT1: port on all clients to the network printer NYCP07 on server PSVR. This example will also install the network printer and set it as the default printer on Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7 clients.

NOTE: When a network printer is installed, the drivers used by the printer are transferred from the server to the client system.

Example:

Filter: Global Settings Action: Disconnect Shared Printer: \\PSVR\ATLP01 Capture Port: Not Selected

The above example will remove the network printer **PSVR\ATLP01** on Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7 clients.

NOTE: When a network printer is removed, the drivers used by the printer are not removed from the client system.



5.1.3.22 RDP Client

This module allows you to configure RDP clients from a centralized location. This module supports RDP versions 4.0 (Windows NT Client), 5.0 (Windows 2000 Client), 5.1 (Windows XP Client), 5.2 (Windows 2003 Client), 6.0 (Windows Vista Client), and 6.1 (Windows 7 Client).

Default	RDP Client - Edit
Filter:	Global Settings
Action:	Create Qverwrite Existing Connection
Connection Name:	
Connection Location:	
Computer:	
User Name:	
Domain:	
Desktop Size:	640 × 480 🔽
Colors:	256 Colors
	Display connection bar in full screen mode
Remote Computer Sound:	Bring to this Computer
Keyboard Combinations:	On the Local Computer 📃
Resources:	🗖 Disk Drives 🔲 Printers
	Serial Ports Smart Cards
	Clipboard I Plug and Play Devices WePOS Devices
C share	the Fellowing Dreaman on Connection
Dath and Filmones	
Faun and Filename:	N/A
Start in Polder:	Madem (28.8 Khar)
Authentication Option:	Always connect, even if authentication fails
TS Gateway Setting:	Automatically detect TS Gateway server settings
Gateway Server Name:	
Logon Method:	Ask for password (NTLM)
-	Bypass TS Gateway server for local addresses
	Reconnect if Connection is Dropped
	OK Cancel

Figure 5.1.3.22: RDP Client



Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Action:

Select one of the following actions:

- Create Creates a new RDP connection.
- Delete Deletes an existing RDP connection.

NOTE: If a client machine has more than one version of the RDP client installed, precedence is given to the newest version. For example, if a client machine has both RDP 4.0 and RDP 5.2 installed, connections will be created and deleted for the RDP 5.2 version.

Overwrite Existing Connection:

When this option is selected, existing RDP connections will be overwritten. This option is only available if Create is selected as the Action.

Connection Name:

Enter the name of the RDP connection you want to create or delete. Subfolders can be specified by entering the relative path followed by the RDP connection name. Surrounding quotes are automatically added to the name.

Connection Location:

Select the location where the RDP connection should be created or deleted.

Computer:

Enter the name of the computer you want the RDP client to connect to. This option is only available if Create is selected as the Action.

User Name:

Enter the user name the RDP client should use when connecting to the server. This option is only available if Create is selected as the Action.

Domain:

Enter the domain name the RDP client should use when connecting to the server. This option is only available if Create is selected as the Action.

Desktop Size:

Select the desktop size the RDP client should use. When the 80% of Screen choice is selected, the RDP desktop size is derived from the client resolution as shown in table 5.1.3.22.1. This option is only available if Create is selected as the Action.

Client Resolution	RDP Desktop Size	
640 x 480	640 x 480	
800 x 600	640 x 480	
1024 x 768	800 x 600	
1280 x 1024	1024 x 768	
1600 x 1200	1280 x 1024	
Table 5.1.3.22.1: 80% of Screen		

Colors:

Select the color depth you want the RDP client to use. This option applies to RDP version 5.1 and newer and is only available if Create is selected as the Action.



Display connection bar in full screen mode:

When this option is selected, the connection bar will be displayed across the top of the display when the RDP connection is in full screen mode. This option applies to RDP version 5.1 and newer and is only available if Create is selected as the Action.

Remote Computer Sound:

Select how you want the RDP client to handle sound. This option applies to RDP version 5.1 and newer and is only available if Create is selected as the Action.

Keyboard Combinations:

Select how you want the RDP client to handle keyboard combinations such as ALT+TAB. This option applies to RDP version 5.1 and newer and is only available if Create is selected as the Action.

Resources:

This option controls the resources that are available to the RDP client. This option applies to RDP version 5.1 and newer and is only available if Create is selected as the Action. Additionally, Clipboard, Plug and Play Devices, and WePOS Devices only applies to RDP version 6.0 and newer.

Start the Following Program on Connection:

Selecting this option instructs the RDP client to start a program on connection. This option is only available if Create is selected as the Action.

Path and Filename:

Enter the full path and filename of the program the RDP client should execute when connecting to the server. This option is only available if Start the Following Program on Connection is selected and Create is selected as the Action.

Start in Folder:

Enter the full path of the folder the RDP client should start in when executing a program on connection to the server. This option is only available if Start the Following Program on Connection is selected and Create is selected as the Action.

Experience:

Select the connection speed you want the RDP client to be optimized for. For RDP version 4.0 and 5.0, selecting Modem (28.8 Kbps) or Modem (56 Kbps) enables the Low Speed Connection option in the RDP client. This option is only available if Create is selected as the Action.

Authentication Option:

Select the server authentication level you want the RDP client to use. This option applies to RDP version 6.0 and newer and is only available if Create is selected as the Action.

TS Gateway Setting:

Select the gateway setting you want the RDP client to use. This option applies to RDP version 6.0 and newer and is only available if Create is selected as the Action.

Gateway Server Name:

Enter the server name of the TS Gateway Server you want the RDP client to use. This option applies to RDP version 6.0 and newer and is only available if Use these TS Gateway server settings is selected and Create is selected as the Action.



Logon Method:

Select the logon method you want the RDP client to use. This option applies to RDP version 6.0 and newer and is only available if Use these TS Gateway server settings is selected and Create is selected as the Action.

Bypass TS Gateway server for local addresses:

Selecting this option instructs the RDP client to bypass the TS Gateway server when the destination is local. This option applies to RDP version 6.0 and newer and is only available if Use these TS Gateway server settings is selected and Create is selected as the Action.

Reconnect if Connection is Dropped:

Selecting this option instructs the RDP client to attempt to automatically reconnect if the connection is dropped. This option applies to RDP version 5.2 and is only available if Create is selected as the Action.

Example:

Filter: Global Settings Action: Delete Connection Name: Accounting\Solomon Connection Location: User Start Menu

The above example deletes the RDP connection named **Solomon** located in the **Accounting** folder in the **User Start Menu**.

Example:

Filter: Global Settings Action: Create **Overwrite Existing Connection: Not Selected** Connection Name: Human Resources\Abra Suite **Connection Location: User Start Menu** Computer: ATLHR User Name: @userid Domain: MyDomain Desktop Size: 80% of Screen Colors: High Color (16 Bit) Display connection bar in full screen mode: Not Selected Remote Computer Sound: Bring to this Computer Keyboard Combinations: On the Local Computer Automatically Connect Disk Drives: Not Selected Automatically Connect Printers: Not Selected Automatically Connect Serial Ports: Not Selected Automatically Connect Smart Cards: Not Selected Start the Following Program on Connection: Selected Path and Filename: C:\Program Files\Best Software\Abra Suite\Programs\Abra32.exe Start in Folder: C:\Program Files\Best Software\Abra Suite\Programs Experience: Broadband (128 Kbps - 1.5 Mbps) Authentication Option: Always connect, even if authentication fails TS Gateway Setting: Automatically detect TS Gateway server settings Reconnect if Connection is Dropped: Selected

The above example creates a RDP connection named Abra Suite. The connection will be created in the User Start Menu in a subfolder named Human Resources. If the connection already exists, it will not be overwritten. This example leverages the macro @userid. When ProfileUnity executes, the @userid macro is expanded into the user's logon name. Therefore,



the created RDP connection will connect to server ATLHR, use the user's logon name as the user name, use domain name MyDomain, use 80% of Screen for the desktop size, and use High Color (16 Bit) color depth. Remote Computer Sound will be brought to the local computer. Keyboard Combinations will stay on the local computer. The RDP connection will start C:\Program Files\Best Software\Abra Suite\Programs\Abra32.exe and start in the C:\Program Files\Best Software\Abra Suite\Programs folder when double clicked. This connection will be optimized for a Broadband (128 Kbps - 1.5 Mbps) network and the connection will automatically reconnect if dropped.

NOTE: Please see section 5.1.2.4 for further assistance with macros.



5.1.3.23 Registry

This module allows you to make changes to the registry on your client machines.

Default		Registry - Edit
Filter:	Global Settings 📃	
Action:	Write Value 💌	
Hive:	HKEY_LOCAL_MACHINE	
Key:		
Type:	REG_BINARY	
Value:		
Data:		
	OK Cancel	

Figure 5.1.3.23: Registry

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Action:

Select one of the following actions:

- Write Value Modifies or creates a value and assigns data to it.
- Delete Value Deletes a value and associated data.
- Add Key Adds the specified key.
- Delete Key Deletes the specified key.

Hive:

Select the registry hive containing the key or value you want to modify.

Key:

Enter the subkey of the Hive you want to modify.

Type:

Select the Type of the Value you want to modify. This option is only available if Write Value is selected as the Action.

Value:

Enter the value you want to modify. This option is only available if Write Value or Delete Value is selected as the Action.

Data:

Enter the data you want assigned to the value. This option is only available if Write Value is selected as the Action.



Example: Filter: Global Settings Action: Add Key Hive: HKEY_CURRENT_USER Key: Software\MyCompany\Test

The above example adds the key **Software\MyCompany\Test** to the **HKEY_CURRENT_USER** hive.

NOTE: The Add Key Action creates missing subkeys automatically. In the above example, the **MyCompany** subkey will be created if it does not already exist.

Example: Filter: Global Settings Action: Write Value Hive: HKEY_CURRENT_USER Key: Software\Microsoft\Windows\CurrentVersion\Internet Settings\Cache Type: REG_DWORD Value: Persistent Data: 0

The above example demonstrates using the Registry module to update Internet Explorer settings. Setting the **Persistent** value to 0 instructs Internet Explorer to empty the temporary Internet files folder when the browser is closed.

NOTE: The Write Value Action creates missing subkeys automatically. In the above example, the subkey **Software\Microsoft\Windows\CurrentVersion\Internet Settings\Cache** will be created if it does not already exist.



5.1.3.24 Shortcuts

This module allows you to create shell shortcuts and web links.

Default		Shortcuts - Edit
Filter:	Global Settings	
Туре:	Shell Shortcut 💌	
Action:	Create 💽 🗖 Overwrite Existing Shortcut	
Shortcut Name:		
Shortcut Location:	User Desktop	
Target:		
Target Arguments:		
Start In:		
Icon File:	Index:	
	OK Cancel	

Figure 5.1.3.24: Shortcuts

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Type:

Select the type of shortcut you want to create or delete. Shell shortcuts are pointers to programs and files on your computer. Web links are used by Internet Explorer for accessing sites on the Internet.

Action:

Select one of the following actions:

- Create Creates a new shortcut.
- Delete Deletes an existing shortcut.

Overwrite Existing Shortcut:

When this option is selected, existing shortcuts will be overwritten. This option is only available if Create is selected as the Action.

Shortcut Name:

Enter the name of the shortcut you want to create or delete. Subfolders can be specified by entering the relative path followed by the shortcut name. Surrounding quotes are automatically added to the name.

Shortcut Location:

Select the location where the shortcut should be created or deleted.



Target:

When creating a Shell Shortcut, enter the full path to the shortcut target. When creating a Web Link, enter the URL you want the link to resolve to. Surrounding quotes are automatically added to the target. This option is only available if Create is selected as the Action.

NOTE: When creating a Shell Shortcut, you must specify the full path in the target. Partial paths are not supported. When creating web links, you must specify the full URL in the target. A full URL starts with http://, https://, or ftp://.

Target Arguments:

Enter any arguments required by the shortcut target. Target Arguments are not automatically quoted. This option is only available if Shell Shortcut is selected as the Type and Create is selected as the Action.

Start In:

Enter the working directory the shortcut target should start in. Surrounding quotes are automatically added to the start in directory. This option is only available if Shell Shortcut is selected as the Type and Create is selected as the Action.

Icon File:

Enter the full path to the icon the shortcut should use. Surrounding quotes are automatically added to the icon file. This option is only available if Shell Shortcut is selected as the Type and Create is selected as the Action.

Index:

If the shortcut icon file contains more than one icon, enter the numerical index of the icon the shortcut should use. This option is only available if Shell Shortcut is selected as the Type and Create is selected as the Action.

Example:

Filter: Global Settings Type: Shell Shortcut Action: Create Overwrite Existing Shortcut: Selected Shortcut Name: Finance\Tax Tables Shortcut Location: User Start Menu Target: P:\Finance\Tax Tables.xls Start In: P:\Finance

The above example creates a shell shortcut named **Tax Tables**. The shortcut will be created in the **User Start Menu** in a subfolder named **Finance**. If the shortcut already exists, it will be overwritten. When double clicked, the shortcut will open **P:\Finance\Tax Tables.xls** in Microsoft Excel.

NOTE: Missing subfolders are created automatically. In the above example, the **Finance** folder will be created if it does not already exist.



Example: Filter: Global Settings Type: Web Link Action: Create Overwrite Existing Shortcut: Not Selected Shortcut Name: Company Intranet Shortcut Location: User Desktop Target: http://int.mycompany.com

The above example creates a web link named Company Intranet on the User Desktop. If the shortcut exists, it is not overwritten. When double clicked, the shortcut will open the website http://int.mycompany.com in Internet Explorer.



5.1.3.25 ThinApp

This module allows you to dynamically provision ThinApp packages.

Default	ThinApp - Edit
Filter: 🛛 Global Settings 💌	
Action: Run from Network	
ThinReg Location:	
ThinApp Package:	
🔲 Keep Unauthorized	
🔲 Don't Register in Add/Remove Programs	
Re-create Shortcuts and Registry Keys	
Remove when Out of Scope	
🔲 Limit Bandwidth to N/A 🛛 Kbps 💌	
OK Cancel	

Figure 5.1.3.25: ThinApp

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Action:

Select one of the following actions:

- Run from Network The ThinApp package is executed from the network location.
- Run from Local Cache The ThinApp package is cached on and runs from the local machine.
- Remove The ThinApp package is removed and the local cache is purged.

ThinReg Location:

Enter the full path to the ThinReg executable.

ThinApp Package:

Enter the full path to the ThinApp package(s). Wildcards are supported.

Keep Unauthorized:

Enabling this option passes the /k switch to ThinReg.

Don't Register in Add/Remove Programs:

Enabling this option passes the /noarp switch to ThinReg.

Re-create Shortcuts and Registry Keys:

Enabling this option passes the /r switch to ThinReg.



Remove when Out of Scope:

Enabling this option will remove the ThinApp package if the selected Filter returns false.

Limit Bandwidth to:

Enabling this option will limit the amount of bandwidth used while caching the ThinApp package on the local machine. This option is only available if Run from Local Cache is chosen for Action.

Example:

Filter: Global Settings Action: Run from Network ThinReg Location: \\file01\thinapps\thinreg.exe ThinApp Package: \\file01\thinapps*.exe Keep Unauthorized: Not Selected Don't Register in Add/Remove Programs: Not Selected Re-create Shortcuts and Registry Keys: Not Selected Remove when Out of Scope: Not Selected

The above example will provision all the ThinApp packages located in \\file01\thinapps on the local machine. Each ThinApp package will be executed from the network.

Example:

Filter: Laptop Users Action: Run from Local Cache ThinReg Location: \\file01\clientapps\thinreg.exe ThinApp Package: \\file01\clientapps\Firefox.exe Keep Unauthorized: Not Selected Don't Register in Add/Remove Programs: Not Selected Re-create Shortcuts and Registry Keys: Not Selected Remove when Out of Scope: Selected Limit Bandwidth to: 1 Mbps

The above example will provision the ThinApp package

\\file01\clientapps\Firefox.exe on the local machine. The ThinApp package will be cached locally using 1 Mbps of bandwidth and will execute from the local cache. Since Remove when Out of Scope has been selected, if the filter Laptop Users returns false, the ThinApp package will be removed.



5.1.3.26 Time Sync

This module allows you to set the time on your client machines from a centralized source. This feature is designed for use with Microsoft clients lacking a native time service. On clients with a native time service, Windows 2000 and newer, the preferred method for setting the client machine's time is to use the time service.

Default		Time Sync - Edit
Filter:	Global Settings	
Time Server	Ølcerver	
Time Server:	wserver	
	OK Cancel	

Figure 5.1.3.26: Time Sync

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Time Server:

Enter the UNC name of the time server the client should set its time from.

NOTE: The recommended setting for the time server is the macro @lserver. The @lserver macro expands during logon into the name of the domain controller processing the logon request. If you use an alternative time server, you will need to use the server's UNC name. For example, if you wanted to use a server name **SVRA1**, you would need to enter **SVRA1** as the time server.

Example:

Filter: Global Settings Time Server: @lserver

The above example synchronizes the client machine's clock with the time obtained from the domain controller processing the logon request.

NOTE: Setting the system time on Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7 requires "Change the system time" right. By default, Users do not have this right.



5.1.3.27 Windows Options

This module allows you to modify settings that control the Windows user interface.

Default		Windows Options - Edit
Filter:	Global Settings	
Rename My Computer:]
Rename My Network Places:]
Wallpaper File:]
	No Change 💌 Command Prompt Here	
	No Change 💌 Tab Auto Complete	
	No Change 💌 Desktop Cleanup Wizard	
	No Change 💌 Remove "Shortcut To" Prefix	
	No Change 💌 Personalized Menus	
	🔲 Sort Start Menu by Name	
	OK Cancel	

Figure 5.1.3.27: Windows Options

Filter:

Select the name of the filter you want assigned to this configuration element. Please see section 3.0 for assistance with filters.

Rename My Computer:

Enter the name you want My Computer renamed to.

NOTE: The recommended setting is the macro @wksta. The @wksta macro expands into the name of the computer during user logon.

Rename My Network Places:

Enter the name you want My Network Places renamed to.

Wallpaper File:

Enter the full path to the bitmap file Windows should use as desktop wallpaper.

NOTE: The wallpaper file must be a bitmap.

Command Prompt Here:

This option enables you to right click a folder in Windows Explorer and choose Command Prompt Here. This action opens a Command Prompt window with the selected folder as your active directory. Available choices are: Enable, Disable, and No Change.



Tab Auto Complete:

This option controls command prompt auto complete functionality. When enabled, you can start typing the name of a file in a command prompt and then press TAB. The shell will attempt to complete the name of the file for you. Available choices are: Enable, Disable, and No Change. This option is only available on Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7.

Desktop Cleanup Wizard:

The Desktop Cleanup Wizard displays a list of the desktop icons that have not been used for 60 days or more, enabling you to remove those icons that you don't want on your desktop. This option allows you to control the Desktop Cleanup Wizard setting used by your users. Available choices are: Enable, Disable, and No Change. This option is only available on Windows XP.

Remove "Shortcut To" Prefix:

This option allows you to remove the "Shortcut to" text prefix on your shortcuts. Available choices are: Enable, Disable, and No Change. This option is only available on Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7.

Personalized Menus:

On clients running Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7, the start menu is automatically updated to keep the items you use most often at the top of the menu where they are usually more accessible. This option allows you to control the Personalized Menus setting used by your users. Available choices are: Enable, Disable, and No Change.

Sort Start Menu by Name:

Selecting this option will sort the Start Menu alphabetically. This option is only available on Windows 2000, Windows XP, Windows 2003, Windows Vista, Windows 2008, and Windows 7.

Example:

Filter: Global Settings Rename My Computer: @wksta Rename My Network Places: Wallpaper File: P:\MyCompany.bmp Command Prompt Here: Enable Tab Auto Complete: Enable Desktop Cleanup Wizard: Disable Remove "Shortcut To" Prefix: No Change Personalized Menus: Disable Sort Start Menu by Name: Selected

The above example renames My Computer to the computer's name, sets the wallpaper file to **P:\MyCompany.bmp**, enables Command Prompt Here, enables Tab Auto Complete, disables the Desktop Cleanup Wizard, disables Personalized Menus, and sorts the Start Menu alphabetically.

NOTE: Leaving a value blank will preserve the current setting. In the above example, My Network Places will not be renamed.



5.2 Delete

Selecting delete will permanently delete the configuration.

5.3 Summary

Summary allows you to generate either a PDF or text summary report of your configuration. The summary report can be instrumental in documenting your network setup.

5.4 Download

After you have finished creating a configuration, it needs to be downloaded to the ProfileUnity folder located in the netlogon share on your domain controller.



6.0 Preferences

This section is used to control various aspects of the ProfileUnity Management Console.

6.1 Backup

You are encouraged to backup your configuration on a regular basis.

PG_DUMP Path: //usr/bin/pg_dump
😋 Indicates Required Field
Backup Config

Figure 6.1.1: Backup Configuration

PG_DUMP Path:

Enter the full path to the pg_dump executable.

NOTE: The ProfileUnity Installer sets this path during installation. If you performed a manual installation, you will need to specify the path to the pg_dump executable before you can backup your configuration.



6.2 Restore

This feature is used to restore previously made backups.

Restore File: Browse	
💭 Indicates Required Field	
Restore Config	
Figure 6.2.1: Restore Configuration	

Restore File:

Browse for the name of the ProfileUnity backup file.



6.3 LDAP Auth

NOTE: This section only applies if you are running the stand alone version of ProfileUnity. If you are running ProfileUnity on the Liquidware Labs virtual appliance please see the Stratusphere Reference Guide for further assistance with this topic.

LDAP Authentication allows users to authenticate against a LDAP directory during ProfileUnity Management Console logon. This feature allows existing directory credentials to be used with ProfileUnity and prevents users from having to maintain an additional password.

Server URI:	ldap://server.xyz.com:3268	
Bind Username:	user@xyz.com	
Bind Password:		
Search Base:	dc=xyz,dc=com	
User Attribute:	samaccountname	
	LDAP Authentication Enabled	
	🕞 Indicates Required Field	
	Save Reset	

Figure 6.3.1: LDAP Auth Configuration

Server URI:

A Server URI consists of the following components: scheme, host, and port. Scheme is either Idap:// or Idaps:// (if SSL is desired). Host is the FQDN or IP Address of the LDAP directory server. Port is the TCP/IP port the LDAP directory server listens for connections on. Multiple LDAP directory servers may be specified by separating entries with commas.

Examples:

ldap://ldap-server.company.com:3268 - Single Server ldap://ldap1.xyz.com:3268, ldap://ldap2.xyz.com:389 - Multiple Servers

Bind Username:

The Bind Username is the user account on the LDAP directory server permitted to search the LDAP directory within the defined search base. Most of the time, the Bind Username will be permitted to search the entire directory. The role of the Bind Username is to search the directory for the user attempting to logon to ProfileUnity. This field can be left blank if anonymous search is desired.



Examples:

cn=Administrator, cn=Users, dc=domain, dc=com - Active Directory DN format
administrator@domain.com - Active Directory User Principal Name format
cn=root, dc=domain, dc=com - OpenLDAP

Bind Password:

The Bind Password is the password used by the Bind Username user account. This field can be left blank if anonymous search is desired.

Search Base:

The Search Base tells the LDAP directory server which part of the directory tree to search. Think of the Search Base as the "top" of the directory for your LDAP users although it may not always the top of the directory itself. The Search Base may be something equivalent to the organization, group, or domain name (AD) of the LDAP directory.

Examples: o=corp - Exchange 5.5 o=corp, c=us - Lotus Domino dc=domain, dc=com - Active Directory, OpenLDAP

User Attribute:

ProfileUnity usernames must map to entries in the LDAP directory server for authentication to succeed. The LDAP directory is searched for the attribute specified in the User Attribute field. For example, ProfileUnity user FredS will need to map to an entry in the LDAP directory having a User Attribute value of FredS.

Examples:

userPrincipalName - Active Directory username with @ symbol 'usera@domain.com' **samAccountName** - Active Directory username without the @ symbol 'usera'

LDAP Authentication Enabled:

This option controls whether LDAP Authentication is Globally Enabled or Disabled. This option must be selected for LDAP Authentication to function.

Active Directory Example:

Server URI: Idap://dc1.company.com:3268, Idap://dc2.company.com:3268 Bind Username: administrator@company.com Bind Password: SuperSecret Search Base: dc=company,dc=com User Attribute: samaccountname LDAP Authentication Enabled: Selected

The above example will search the global catalog (Port: 3268) for the samaccountname attribute on servers dc1.company.com and dc2.company.com. The search will be performed as user administrator@company.com with password SuperSecret. The search will include all accounts in the LDAP directory (Search Base: dc=company.dc=com).


6.4 Inventory

These settings control the behavior of the Inventory Reporting feature.

Purge Records Older than 30 👘 Days 😪
Inventory Purge Enabled
🤤 Indicates Required Field
Save Reset

Figure 6.4.1: Inventory Configuration

Purge Records Older than ____ days:

The Inventory Purge feature keeps your records clean by removing entries that are older than a set number of days.

Inventory Purge Enabled:

This option controls whether Inventory Purge is Globally Enabled or Disabled. This option must be selected for Inventory Purge to function.

Example:

Purge Records Older than ____ days: 30 Inventory Purge Enabled: Selected

The above example will remove records from the Inventory Reporting feature that have not been refreshed in the last 30 days.



7.0 Inventory

This feature is used to view reports about the hardware, software, and ThinApp inventory retrieved by ProfileUnity.

7.1 System

	Timestamp	<u>Computer Name</u>	<u>Domain</u>	<u>Username</u>
Delete Details	10/20/2009	HYDRA	ENTRIGUE	ISTest
Displaying 1 of 1				

Figure 7.1: System Inventory

7.1.1 Delete

Selecting delete will permanently delete the chosen record.

NOTE: The Inventory Purge feature is designed to automatically delete old records. Please see section 6.3 for further information.

7.1.2 Details

Selecting details will display an in depth hardware and software inventory report for the chosen record.

7.2 ThinApp

	Device	User	App Name	App Path
Delete Details	1	1	Safari_en.exe	\\file01.tntatl.internal\us
Delete Details	2	1	VLC media player Win7.exe	\\file01.tntatl.internal\us
Delete Details	1	1	VMware Infrastructure Clien	\\file01.tntatl.internal\us
Delete Details	2	1	WinSCP.exe	\\file01.tntatl.internal\us
Displaying 1-4 (of 4			

Figure 7.2: ThinApp Inventory

7.2.1 Delete

Selecting delete will permanently delete the chosen record.

NOTE: The Inventory Purge feature is designed to automatically delete old records. Please see section 6.3 for further information.

7.2.2 Details

Selecting details will display an in depth inventory report for the chosen ThinApp package.



8.0 User Management

NOTE: This section only applies if you are running the stand alone version of ProfileUnity. If you are running ProfileUnity on the Liquidware Labs virtual appliance please see the Stratusphere Reference Guide for further assistance with this topic.

A valid user account is required to logon to the ProfileUnity Management Console. Creating, modifying, and deleting user accounts is done through the user management interface, shown in figure 8.0.1.

New User	Username	Account Type	Auth Type	Last Logon
Edit Delete	admin	Administrator	Local	01/08/2010
Reset Password				
Edit Delete	test	User	Disabled	N/A
Reset Password				
Displaying 1-2 of 2				

Figure 8.0.1: User Management Interface



8.1 User Editor

The user editor, shown in figure 8.1.1, is where all user configuration takes place. Selecting the following options in the user management interface invokes the user editor:

- New User Creates a new user account
- Edit Modifies an existing user account

Edit User	
Username:	
Password:	
Confirm Password:	
	LDAP Authentication
	Administrator
	Account Disabled
	🤤 Indicates Required Field
	Save Reset

Figure 8.1.1: User Editor Interface

Username:

Enter the username the user will use to logon to ProfileUnity.

NOTE: If LDAP Authentication is selected, this username must map to an entry in the LDAP directory server for authentication to succeed. Please see section 6.3 for further assistance.

Password:

Enter the password the user will use to logon to ProfileUnity. This field is not used if LDAP Authentication is selected.

Confirm Password:

Confirm the password the user will use to logon to ProfileUnity. This field is not used if LDAP Authentication is selected.

LDAP Authentication:

This option controls whether LDAP Authentication is Enabled or Disabled.

Administrator:

Selecting this option grants the account privileges to manage user accounts and configuration settings.

Account Disabled:

Selecting this option prevents the user from logging on.



Example: Username: JohnD Password: pass1234 Confirm Password: pass1234 LDAP Authentication: Not Selected Administrator: Selected Account Disabled: Not Selected

The above example will add an account with username **JohnD** and password **pass1234**. Since **Administrator** has been selected, this account will be able to manage user accounts and configuration settings.

8.2 Delete

Selecting delete will permanently delete the user account.

8.3 Reset Password

Reset Password allows the password for the user account to be changed.



9.0 Support / Contact Information

Please visit <u>http://www.profileunity.com</u> for the latest support and contact information or send email to <u>support@profileunity.com</u>.



10.0 Acknowledgements

ProfileUnity is built on the KiXtart scripting language developed by Mr. Ruud van Velsen. Liquidware Labs, Inc. would like to extend its heartfelt gratitude to Mr. Ruud van Velsen for developing and allowing us to incorporate KiXtart into the ProfileUnity product.

ProfileUnity uses AES encryption and decryption routines written by Dr. Brian Gladman. The source code for these routines is available to any interested party from the AES project page on Dr. Gladman's web site. This is the same AES code that is incorporated into ProfileUnity. Liquidware Labs, Inc. would like to express its appreciation to Dr. Gladman for making this code available.



Appendix A - Custom Functions

The Custom Function filter condition allows filter logic to be extended through the use of a custom written KiXtart function. There are 3 steps required to setup and use this feature.

Step 1:

Write a custom KiXtart function that returns 1 on success and 0 on failure. Save this function into a file located in the netlogon share on your domain controller.

Example:

function demo(\$var, \$val)				
if (\$var = \$val)				
; return 1 on				
success				
\$demo = 1				
else				
; return 0 on failure				
\$demo = 0				
endif				
endfunction				

Step 2:

Include the file containing the custom function in your configuration.

New Configuration		User Defined Scripts - Edit
Execute	Before ProfileUnity (Pre-Execution) 👤	
File	@lserver\netlogon\my_function.kix]
	Run In-Process	
	OK Cancel	

Figure A.1: Include Custom Function

Example:

Execute: Before ProfileUnity File: @lserver\netlogon\my_function.kix Run In-Process: Selected



Step 3:

Build a filter that uses the custom function.

Create/Edit Filter		
Filter Name: My C Filter Comment: Rule Aggregate: AND	ustom Function (All Rules) 💌 😪	
	Filter Rules	
Condition Ma	tch Value	
Custom Function 💽 Is (Exactly) 📃 🔄 demo(%ENVVAR%, "som	e value") Add
Machine Class ✓ Desktop / Laptop ✓ Terminal Server ✓ Member Server ✓ Domain Controller	Operating System ✓ 2000 ✓ Vista ✓ XP ✓ 2008 ✓ 2003 ✓ 7	Connection LAN Dial-up/VPN
	C Indicates Required Field	

Figure A.2: Custom Function Filter

Example:

demo(%ENVVAR%, "some value")



Appendix B - Alternative Client Install Path

By default, the ProfileUnity client installs to the netlogon share on your domain controller. This path is recommended but is not required. The netlogon share is a DFS replicated path that is available on all properly functioning domain controllers. Installing ProfileUnity to this path prevents a single point of failure. If at least one domain controller is online ProfileUnity can operate. Additionally this path allows ProfileUnity to scale through load distribution across domain controllers.

If you choose to install the ProfileUnity client to an alternative UNC path you will need to perform the following two steps:

Step 1

Specify the alternative UNC path when running the client installer. Please see section 1.2 for further assistance.

Step 2

Specify the alternative UNC path when configuring group policy. You will need to specify this path for the startup script, the INI File Path, and the logoff script. Please see section 2.0 for further assistance.

NOTE: The group policy startup script will execute using the computer's credentials. The ProfileUnity client and the group policy logoff script will execute using the user's credentials. The recommended way to setup the alternative UNC path is to allow either Authenticated Users or Everyone read access. This permission setup will allow both the computer and the user to access ProfileUnity.



Appendix C - KiXtart: Do You Care?

The following is an excerpt from the KiXtart help manual written by Mr. Ruud van Velsen.

Introduction

KiXtart was started in 1991 as a spare time project in response to the many requests for logon scripting functionality for the Microsoft LAN Manager environment. KiXtart's simplicity, speed and lack of competition soon made it very popular with LAN Manager network administrators.

KiXtart was initially distributed as freeware through bulletin boards in Europe. Later, Internet sites picked up on KiXtart and started distribution lists, discussion forums and script archives. KiXtart was also shipped as part of several Microsoft Resource Kits. Over time, KiXtart grew, both in popularity as well as in functionality. Windows NT and Windows 95 support was added, as well as lots of new functions and features.

Today, thousands of organizations worldwide use KiXtart. Banks, insurance companies, colleges, universities, hospitals, power plants, governmental organizations, IT companies, car manufacturers, oil companies, aerospace industries, publishers, amusement parks, broadcasting companies, and numerous other types of organizations around the globe make daily use of KiXtart to configure workstations, install software, and perform many other scripting tasks.

KiXtart has also become a hot topic on various Internet discussion forums, with many enthusiastic participants sharing tips, tricks and scripts.

Over the years, many people have asked when KiXtart would be commercialized. In fact, requests for pricing and licensing information on KiXtart are quite common.

If nothing else, all of this proves that KiXtart has a value.

Rather than commercializing KiXtart, I would like to turn its value into something truly positive. Specifically, I would like to use its value to help people who absolutely need and deserve our support: the people of Nepal.

As part of this initiative, KiXtart 2001 is provided to you as so-called CareWare. Exactly what this means is detailed in the following paragraphs. Please read the information carefully and support the KiXtart CareWare initiative!

What is CareWare?

CareWare is a variant on shareware and freeware. It is sometimes also known as 'charityware', 'donationware', 'helpware' or 'goodware', and is copyrighted software that you are allowed to use at no charge in return for a donation to specified charity/ies or to a charity of the users' choice.

KiXtart CareWare can be downloaded, installed and evaluated at no charge. If you continue using KiXtart, you are kindly requested to make a donation to a non-profit charitable organization. A list of preferred charities is provided below.

How much should we donate?

The answer to this question is in your heart. The donation amount should reflect your perception of the value of KiXtart for your organization. The suggested minimum donation amount is fifty US dollars (\$50) per organization/company using KiXtart. Please consider that CareWare is not about making money, but about sharing with and caring for other people.

Making a donation is more important than the actual amount of the donation.



Note that in many countries, charitable donations to officially registered charities are tax deductible, so you may be able to donate more than you think!

Who should we donate to?

The following non-profit, charitable organizations that support the people in Nepal are preferred:





If, for whatever reason, you can not donate to these particular organizations, you are kindly requested to donate to Unicef instead:





For more than 53 years UNICEF has been helping governments, communities and families make the world a better place for children. Part of the United Nations system, UNICEF has an enviable mandate and mission, to advocate for children's rights and help meet their needs.

Note: more details on these organizations can be found in the GuideStar directory: <u>http://www.guidestar.org</u>.

Why Nepal?

When I visited Nepal in 1999, I became enchanted with its magnificent beauty and its kind and hospitable people. At the same time, I was stunned by the poverty.

Nepal, home of Mount Everest, is one of the poorest countries in the world in relative as well as absolute terms. More than half of the population lives below the poverty line and 53% of the people live on less than US\$ 1 per day. Nepal has few natural resources apart from its beauty and hardworking people. Life expectancy is very low, and illiteracy affects more than 50% of the children. Education, medication, and even basic things such as clean water are a luxury in large parts of Nepal. Malnutrition is another widespread problem: everyday, a Nepali child goes blind for want of vitamin A, something that can be prevented by a medicine costing less than ten cents.

What do I get in return?

Of course, the whole concept of CareWare is about giving, not receiving. However, making a donation on behalf of KiXtart provides the following benefits:

- People elsewhere in the world benefit from your support.
- You get to feel good about using KiXtart.
- You motivate me to continue developing KiXtart.

Additionally, if you choose to register your donation, you will be kept up to date on KiXtart developments, and your (company) name can be included on the list of KiXtart CareWare sponsors. See below for details on how to register your donation.

How should we make a donation?

To make a donation, simply select the organization you would like to support, determine the amount you can donate, and use one of the donation methods supported by the organization.

When you make a donation, please include a reference to "KiXtart 2001".

Optionally, you can also register your donation by forwarding the confirmation email you send to or receive from the charitable organization to <u>kixtart2001@hotmail.com</u> or <u>ruudv@microsoft.com</u>.

I can't make a donation to charity!

If you are not able to donate money to any charity, for whatever reason, I would appreciate it if you could let me know why. Understanding what the problem with making a donation is will enable me to improve the KiXtart CareWare process.



I don't care...

That is entirely your prerogative. The KiXtart CareWare initiative is based on your voluntary cooperation. KiXtart has no built-in registration process or license checks.

Please carefully consider the value of KiXtart to you and your organization, and reconsider making a donation. Your support will be greatly appreciated, by me, and more importantly, by the organizations you donate to and the people they support. Join the growing number of KiXtart CareWare supporters today!